

---

**RsSgt**

***Release 5.0.232.31***

**Rohde & Schwarz**

**Mar 25, 2024**



## CONTENTS:

<b>1</b>	<b>Revision History</b>	<b>3</b>
1.1	RsSgt . . . . .	3
1.1.1	Version history: . . . . .	3
<b>2</b>	<b>Getting Started</b>	<b>5</b>
2.1	Introduction . . . . .	5
2.2	Installation . . . . .	6
2.3	Finding Available Instruments . . . . .	7
2.4	Initiating Instrument Session . . . . .	8
2.5	Plain SCPI Communication . . . . .	11
2.6	Error Checking . . . . .	14
2.7	Exception Handling . . . . .	14
2.8	Transferring Files . . . . .	16
2.9	Writing Binary Data . . . . .	16
2.10	Transferring Big Data with Progress . . . . .	17
2.11	Multithreading . . . . .	18
2.12	Logging . . . . .	21
<b>3</b>	<b>Enums</b>	<b>25</b>
3.1	AttMode . . . . .	25
3.2	BbSystemConfiguration . . . . .	25
3.3	CalPowDetAtt . . . . .	25
3.4	FreqStepMode . . . . .	25
3.5	ImpG50G10K . . . . .	26
3.6	InclExcl . . . . .	26
3.7	InputImpRf . . . . .	26
3.8	IqMode . . . . .	26
3.9	OpMode . . . . .	26
3.10	PowAlcState . . . . .	27
3.11	PowLevBehaviour . . . . .	27
3.12	PowLevMode . . . . .	27
3.13	PowOutpPonMode . . . . .	27
3.14	PowRfOffMode . . . . .	27
3.15	PowSensWithUndef . . . . .	28
3.16	RefLoOutput . . . . .	28
3.17	RoscFreqExt . . . . .	28
3.18	SlopeType . . . . .	28
3.19	SourceInt . . . . .	28
3.20	Test . . . . .	29
3.21	UserPlug . . . . .	29

<b>4</b>	<b>RepCaps</b>	<b>31</b>
4.1	HwInstance (Global)	31
4.2	BitNumberNull	31
4.3	IqConnector	31
4.4	UserIx	32
<b>5</b>	<b>Examples</b>	<b>33</b>
<b>6</b>	<b>RsSgt API Structure</b>	<b>39</b>
6.1	Calibration	43
6.1.1	All	43
6.1.2	Frequency	44
6.1.3	IqModulator	44
6.1.3.1	Bband	45
6.1.3.2	IqModulator	46
6.1.4	Level	46
6.2	Connector	47
6.2.1	RefLo	47
6.2.2	User<UserIx>	48
6.2.2.1	Clock	48
6.2.2.1.1	Impedance	48
6.2.2.1.2	Slope	49
6.2.2.2	Omode	50
6.2.2.3	Threshold	51
6.2.2.4	Trigger	51
6.2.2.4.1	Impedance	51
6.2.2.4.2	Slope	52
6.3	Diagnostic	53
6.3.1	Point	53
6.4	MassMemory	54
6.4.1	Catalog	56
6.4.1.1	Length	57
6.4.2	Dcatalog	57
6.4.2.1	Length	58
6.4.3	Load	58
6.4.3.1	State	59
6.4.4	Store	59
6.4.4.1	State	59
6.5	Output	60
6.5.1	Afixed	61
6.5.1.1	Range	61
6.5.2	Protection	62
6.5.3	State	62
6.6	Sconfiguration	63
6.7	Source	64
6.7.1	Bb	64
6.7.1.1	Impairment	66
6.7.1.1.1	Bbmm<IqConnector>	66
6.7.1.1.1.1	Poffset	66
6.7.1.1.2	IqOutput<IqConnector>	67
6.7.1.1.2.1	IqRatio	67
6.7.1.1.2.2	Magnitude	68
6.7.1.1.2.3	Leakage	69
6.7.1.1.2.4	Icomponent	69

	6.7.1.1.2.5	Qcomponent . . . . .	70
	6.7.1.1.2.6	Quadrature . . . . .	71
	6.7.1.1.2.7	Angle . . . . .	71
	6.7.1.1.2.8	State . . . . .	72
6.7.2	Bbin . . . . .		73
6.7.2.1	SymbolRate . . . . .		74
6.7.3	Frequency . . . . .		74
6.7.3.1	Cw . . . . .		75
	6.7.3.1.1 Step . . . . .		76
6.7.3.2	Fixed . . . . .		77
	6.7.3.2.1 Step . . . . .		78
6.7.4	InputPy . . . . .		79
6.7.4.1	Modext . . . . .		79
6.7.4.2	Trigger . . . . .		80
	6.7.4.2.1 Bband . . . . .		81
6.7.5	Iq . . . . .		81
6.7.5.1	Impairment . . . . .		83
	6.7.5.1.1 IqRatio . . . . .		84
	6.7.5.1.2 Leakage . . . . .		84
	6.7.5.1.3 Quadrature . . . . .		85
	6.7.5.1.4 Swap . . . . .		86
6.7.6	Loscillator . . . . .		86
6.7.7	Phase . . . . .		87
6.7.7.1	Reference . . . . .		88
6.7.8	Power . . . . .		88
6.7.8.1	Alc . . . . .		90
	6.7.8.1.1 Sonce . . . . .		91
6.7.8.2	Attenuation . . . . .		92
	6.7.8.2.1 RfOff . . . . .		92
	6.7.8.2.2 Sover . . . . .		93
6.7.8.3	Level . . . . .		94
	6.7.8.3.1 Immediate . . . . .		94
6.7.8.4	Limit . . . . .		95
6.7.8.5	Range . . . . .		96
6.7.8.6	Servoing . . . . .		96
	6.7.8.6.1 Sensor . . . . .		99
6.7.9	Roscillator . . . . .		100
6.7.9.1	External . . . . .		100
6.7.9.2	Output . . . . .		101
6.8	Status . . . . .		102
6.8.1	Operation . . . . .		102
	6.8.1.1 Bit<BitNumberNull> . . . . .		105
		6.8.1.1.1 Condition . . . . .	105
		6.8.1.1.2 Enable . . . . .	106
		6.8.1.1.3 Event . . . . .	106
		6.8.1.1.4 Ntransition . . . . .	107
		6.8.1.1.5 Ptransition . . . . .	107
6.8.2	Questionable . . . . .		108
	6.8.2.1 Bit<BitNumberNull> . . . . .		110
		6.8.2.1.1 Condition . . . . .	111
		6.8.2.1.2 Enable . . . . .	111
		6.8.2.1.3 Event . . . . .	112
		6.8.2.1.4 Ntransition . . . . .	112
		6.8.2.1.5 Ptransition . . . . .	113

6.8.3	Queue . . . . .	114
6.9	System . . . . .	114
6.9.1	Date . . . . .	117
6.9.2	Device . . . . .	118
6.9.3	DeviceFootprint . . . . .	118
6.9.3.1	History . . . . .	119
6.9.4	Error . . . . .	119
6.9.4.1	Code . . . . .	120
6.9.5	Fpreset . . . . .	121
6.9.6	Help . . . . .	121
6.9.6.1	Syntax . . . . .	122
6.9.7	Lock . . . . .	122
6.9.7.1	Name . . . . .	123
6.9.7.2	Owner . . . . .	124
6.9.7.3	Release . . . . .	124
6.9.7.4	Request . . . . .	125
6.9.7.4.1	Shared . . . . .	125
6.9.7.5	Shared . . . . .	126
6.9.8	Time . . . . .	126
6.9.8.1	DaylightSavingTime . . . . .	127
6.9.8.1.1	Rule . . . . .	128
6.9.8.2	HrTimer . . . . .	129
6.9.8.2.1	Absolute . . . . .	129
6.10	Test . . . . .	130
6.10.1	All . . . . .	130
6.10.2	Keyboard . . . . .	131
<b>7</b>	<b>RsSgt Utilities</b>	<b>133</b>
<b>8</b>	<b>RsSgt Logger</b>	<b>139</b>
<b>9</b>	<b>RsSgt Events</b>	<b>141</b>
<b>10</b>	<b>Index</b>	<b>143</b>
	<b>Index</b>	<b>145</b>







## REVISION HISTORY

### 1.1 RsSgt

Rohde & Schwarz SGT100A SIGMA Vector Signal Generator RsSgt instrument driver.

Basic Hello-World code:

```
from RsSgt import *  
  
instr = RsSgt('TCPIP::192.168.2.101::hislip0')  
idn = instr.query('*IDN?')  
print('Hello, I am: ' + idn)
```

Supported instruments: SGT100A

The package is hosted here: <https://pypi.org/project/RsSgt/>

Documentation: <https://RsSgt.readthedocs.io/>

Examples: [https://github.com/Rohde-Schwarz/Examples/tree/main/SignalGenerators/Python/RsSgt\\_ScpiPackage](https://github.com/Rohde-Schwarz/Examples/tree/main/SignalGenerators/Python/RsSgt_ScpiPackage)

#### 1.1.1 Version history:

Latest release notes summary: Update for FW 5.0.232, removed legacy option XM Radio

##### Version 5.0.232

- Update for FW 5.0.232
- Removed legacy option XM Radio

##### Version 4.90.109

- Updated for FW 4.90
- Updated core to the newest template.
- Added DigitalModulation Interface.

**Version 4.80.1.25**

- Fixed bug in interfaces with the name 'base'

**Version 4.80.1.22**

- Fixed several misspelled arguments and command headers

**Version 4.80.1.19**

- Complete rework of the Repeated capabilities. Before, the driver used extensively the RepCaps Channel, Stream, Subframe, User, Group. Now, they have more fitting names, and also proper ranges and default values.
- All the repcaps ending with Null have ranges starting with 0. 0 is also their default value. For example, ChannelNull starts from 0, while Channel starts from 1. Since this is a breaking change, please make sure your code written in the previous version of the driver is compatible with this new version. This change was necessary in order to assure all the possible settings.

**Version 4.80.0.16**

- Added arb\_files interface
- Default HwInterface repcap is 0 (empty command suffix)

**Version 4.80.0.5**

- First released version

## GETTING STARTED

### 2.1 Introduction



**RsSgt** is a Python remote-control communication module for Rohde & Schwarz SCPI-based Test and Measurement Instruments. It represents SCPI commands as fixed APIs and hence provides SCPI autocompletion and helps you to avoid common string typing mistakes.

Basic example of the idea:

SCPI command:

SYSTem:REFeRence:FREQuency:SOURce

Python module representation:

writing:

```
driver.system.reference.frequency.source.set()
```

reading:

```
driver.system.reference.frequency.source.get()
```

Check out this RsSgt example:

```
"""Getting started - how to work with RsSgt Python package.
This example performs basic RF settings on an SGT100A instrument.
It shows the RsSgt calls and their corresponding SCPI commands.
Notice that the python RsSgt interfaces track the SCPI commands syntax."""
```

```
from RsSgt import *

# Open the session
sgt = RsSgt('TCPIP::10.112.0.228::HISLIP')
# Greetings, stranger...
print(f'Hello, I am: {sgt.utilities.idn_string}')

# OUTPut:STATe ON
sgt.output.state.set_value(True)

# SOURce:POWer:LEVel:IMMediate:AMPLitude -25
sgt.source.power.level.immediate.set_amplitude(-25)
```

(continues on next page)

(continued from previous page)

```
# SOURCE:FREquency:FIXed 11000000000
sgt.source.frequency.fixed.set_value(1.1E9)

# SOURCE:POWer:PEP?
pep = sgt.source.power.get_pep()
print(f'PEP level: {pep} dBm')

# Close the session
sgt.close()
```

Couple of reasons why to choose this module over plain SCPI approach:

- Type-safe API using typing module
- You can still use the plain SCPI communication
- You can select which VISA to use or even not use any VISA at all
- Initialization of a new session is straight-forward, no need to set any other properties
- Many useful features are already implemented - reset, self-test, opc-synchronization, error checking, option checking
- Binary data blocks transfer in both directions
- Transfer of arrays of numbers in binary or ASCII format
- File transfers in both directions
- Events generation in case of error, sent data, received data, chunk data (for big files transfer)
- Multithreading session locking - you can use multiple threads talking to one instrument at the same time
- Logging feature tailored for SCPI communication - different for binary and ascii data

## 2.2 Installation

RsSgt is hosted on [pypi.org](https://pypi.org). You can install it with pip (for example, `pip.exe` for Windows), or if you are using Pycharm (and you should be :-)) direct in the Pycharm `Package Management` GUI.

### Preconditions

- Installed VISA. You can skip this if you plan to use only socket LAN connection. Download the Rohde & Schwarz VISA for Windows, Linux, Mac OS from [here](#)

### Option 1 - Installing with pip.exe under Windows

- Start the command console: WinKey + R, type cmd and hit ENTER
- Change the working directory to the Python installation of your choice (adjust the user name and python version in the path):

```
cd c:\Users\John\AppData\Local\Programs\Python\Python37\Scripts
```

- Install with the command: `pip install RsSgt`

### Option 2 - Installing in Pycharm

- In Pycharm Menu File->Settings->Project->Project Interpreter click on the '+' button on the top left (the last PyCharm version)
- Type RsSgt in the search box
- If you are behind a Proxy server, configure it in the Menu: File->Settings->Appearance->System Settings->HTTP Proxy

For more information about Rohde & Schwarz instrument remote control, check out our [Instrument Remote Control Web Series](#).

### Option 3 - Offline Installation

If you are still reading the installation chapter, it is probably because the options above did not work for you - proxy problems, your boss saw the internet bill... Here are 6 steps for installing the RsSgt offline:

- Download this python script (**Save target as**): `rsinstrument_offline_install.py` This installs all the preconditions that the RsSgt needs.
- Execute the script in your offline computer (supported is python 3.6 or newer)
- Download the RsSgt package to your computer from the pypi.org: <https://pypi.org/project/RsSgt/#files> to for example `c:\temp\`
- Start the command line WinKey + R, type cmd and hit ENTER
- Change the working directory to the Python installation of your choice (adjust the user name and python version in the path):

```
cd c:\Users\John\AppData\Local\Programs\Python\Python37\Scripts
```

- Install with the command: `pip install c:\temp\RsSgt-5.0.232.31.tar`

## 2.3 Finding Available Instruments

Like the pyvisa's ResourceManager, the RsSgt can search for available instruments:

```
"""
Find the instruments in your environment
"""

from RsSgt import *

# Use the instr_list string items as resource names in the RsSgt constructor
```

(continues on next page)

(continued from previous page)

```
instr_list = RsSgt.list_resources("?*")
print(instr_list)
```

If you have more VISAs installed, the one actually used by default is defined by a secret widget called Visa Conflict Manager. You can force your program to use a VISA of your choice:

```
"""
Find the instruments in your environment with the defined VISA implementation
"""

from RsSgt import *

# In the optional parameter visa_select you can use for example 'rs' or 'ni'
# Rs Visa also finds any NRP-Zxx USB sensors
instr_list = RsSgt.list_resources('*.*', 'rs')
print(instr_list)
```

---

**Tip:** We believe our R&S VISA is the best choice for our customers. Here are the reasons why:

- Small footprint
  - Superior VXI-11 and HiSLIP performance
  - Integrated legacy sensors NRP-Zxx support
  - Additional VXI-11 and LXI devices search
  - Availability for Windows, Linux, Mac OS
- 

## 2.4 Initiating Instrument Session

RsSgt offers four different types of starting your remote-control session. We begin with the most typical case, and progress with more special ones.

### Standard Session Initialization

Initiating new instrument session happens, when you instantiate the RsSgt object. Below, is a simple Hello World example. Different resource names are examples for different physical interfaces.

```
"""
Simple example on how to use the RsSgt module for remote-controlling your instrument
Preconditions:

- Installed RsSgt Python module Version 5.0.232 or newer from pypi.org
- Installed VISA, for example R&S Visa 5.12 or newer
"""

from RsSgt import *

# A good practice is to assure that you have a certain minimum version installed
```

(continues on next page)

(continued from previous page)

```
RsSgt.assert_minimum_version('5.0.232')
resource_string_1 = 'TCPIP::192.168.2.101::INSTR' # Standard LAN connection (also
↳ called VXI-11)
resource_string_2 = 'TCPIP::192.168.2.101::hislip0' # Hi-Speed LAN connection - see
↳ 1MA208
resource_string_3 = 'GPIB::20::INSTR' # GPIB Connection
resource_string_4 = 'USB::0x0AAD::0x0119::022019943::INSTR' # USB-TMC (Test and
↳ Measurement Class)

# Initializing the session
driver = RsSgt(resource_string_1)

idn = driver.utilities.query_str('*IDN?')
print(f"\nHello, I am: '{idn}'")
print(f'RsSgt package version: {driver.utilities.driver_version}')
print(f'Visa manufacturer: {driver.utilities.visa_manufacturer}')
print(f'Instrument full name: {driver.utilities.full_instrument_model_name}')
print(f'Instrument installed options: {",".join(driver.utilities.instrument_options)}')

# Close the session
driver.close()
```

**Note:** If you are wondering about the missing ASRL1::INSTR, yes, it works too, but come on... it's 2023.

Do not care about specialty of each session kind; RsSgt handles all the necessary session settings for you. You immediately have access to many identification properties in the interface `driver.utilities`. Here are some of them:

- `idn_string`
- `driver_version`
- `visa_manufacturer`
- `full_instrument_model_name`
- `instrument_serial_number`
- `instrument_firmware_version`
- `instrument_options`

The constructor also contains optional boolean arguments `id_query` and `reset`:

```
driver = RsSgt('TCPIP::192.168.56.101::hislip0', id_query=True, reset=True)
```

- Setting `id_query` to `True` (default is `True`) checks, whether your instrument can be used with the RsSgt module.
- Setting `reset` to `True` (default is `False`) resets your instrument. It is equivalent to calling the `reset()` method.

## Selecting a Specific VISA

Just like in the function `list_resources()`, the RsSgt allows you to choose which VISA to use:

```
"""
Choosing VISA implementation
"""

from RsSgt import *

# Force use of the Rs Visa. For NI Visa, use the "SelectVisa='ni'"
driver = RsSgt('TCPIP::192.168.56.101::INSTR', True, True, "SelectVisa='rs'")

idn = driver.utilities.query_str('*IDN?')
print(f"\nHello, I am: '{idn}'")
print(f"\nI am using the VISA from: {driver.utilities.visa_manufacturer}")

# Close the session
driver.close()
```

## No VISA Session

We recommend using VISA when possible preferably with HiSlip session because of its low latency. However, if you are a strict VISA denier, RsSgt has something for you too - **no Visa installation raw LAN socket**:

```
"""
Using RsSgt without VISA for LAN Raw socket communication
"""

from RsSgt import *

driver = RsSgt('TCPIP::192.168.56.101::5025::SOCKET', True, True, "SelectVisa='socket'")
print(f'Visa manufacturer: {driver.utilities.visa_manufacturer}')
print(f"\nHello, I am: '{driver.utilities.idn_string}'")

# Close the session
driver.close()
```

**Warning:** Not using VISA can cause problems by debugging when you want to use the communication Trace Tool. The good news is, you can easily switch to use VISA and back just by changing the constructor arguments. The rest of your code stays unchanged.



## Simulating Session

If a colleague is currently occupying your instrument, leave him in peace, and open a simulating session:

```
driver = RsSgt('TCPIP::192.168.56.101::hislip0', True, True, "Simulate=True")
```

More option\_string tokens are separated by comma:

```
driver = RsSgt('TCPIP::192.168.56.101::hislip0', True, True, "SelectVisa='rs',  
↳ Simulate=True")
```

## Shared Session

In some scenarios, you want to have two independent objects talking to the same instrument. Rather than opening a second VISA connection, share the same one between two or more RsSgt objects:

```
"""
Sharing the same physical VISA session by two different RsSgt objects
"""

from RsSgt import *

driver1 = RsSgt('TCPIP::192.168.56.101::INSTR', True, True)
driver2 = RsSgt.from_existing_session(driver1)

print(f'driver1: {driver1.utilities.idn_string}')
print(f'driver2: {driver2.utilities.idn_string}')

# Closing the driver2 session does not close the driver1 session - driver1 is the
↳ 'session master'
driver2.close()
print(f'driver2: I am closed now')

print(f'driver1: I am still opened and working: {driver1.utilities.idn_string}')
driver1.close()
print(f'driver1: Only now I am closed.')
```

**Note:** The driver1 is the object holding the ‘master’ session. If you call the driver1.close(), the driver2 loses its instrument session as well, and becomes pretty much useless.

## 2.5 Plain SCPI Communication

After you have opened the session, you can use the instrument-specific part described in the RsSgt API Structure. If for any reason you want to use the plain SCPI, use the utilities interface’s two basic methods:

- write\_str() - writing a command without an answer, for example \*RST
- query\_str() - querying your instrument, for example the \*IDN? query

You may ask a question. Actually, two questions:

- Q1: Why there are not called write() and query() ?

- **Q2:** Where is the read() ?

**Answer 1:** Actually, there are - the `write_str()` / `write()` and `query_str()` / `query()` are aliases, and you can use any of them. We promote the `_str` names, to clearly show you want to work with strings. Strings in Python3 are Unicode, the *bytes* and *string* objects are not interchangeable, since one character might be represented by more than 1 byte. To avoid mixing string and binary communication, all the method names for binary transfer contain `_bin` in the name.

**Answer 2:** Short answer - you do not need it. Long answer - your instrument never sends unsolicited responses. If you send a set command, you use `write_str()`. For a query command, you use `query_str()`. So, you really do not need it...

**Bottom line** - if you are used to `write()` and `query()` methods, from `pyvisa`, the `write_str()` and `query_str()` are their equivalents.

Enough with the theory, let us look at an example. Simple write, and query:

```
"""
Basic string write_str / query_str
"""

from RsSgt import *

driver = RsSgt('TCPIP::192.168.56.101::INSTR')
driver.utilities.write_str('*RST')
response = driver.utilities.query_str('*IDN?')
print(response)

# Close the session
driver.close()
```

This example is so-called “*University-Professor-Example*” - good to show a principle, but never used in praxis. The abovementioned commands are already a part of the driver’s API. Here is another example, achieving the same goal:

```
"""
Basic string write_str / query_str
"""

from RsSgt import *

driver = RsSgt('TCPIP::192.168.56.101::INSTR')
driver.utilities.reset()
print(driver.utilities.idn_string)

# Close the session
driver.close()
```

One additional feature we need to mention here: **VISA timeout**. To simplify, VISA timeout plays a role in each `query_xxx()`, where the controller (your PC) has to prevent waiting forever for an answer from your instrument. VISA timeout defines that maximum waiting time. You can set/read it with the `visa_timeout` property:

```
# Timeout in milliseconds
driver.utilities.visa_timeout = 3000
```

After this time, the `RsSgt` raises an exception. Speaking of exceptions, an important feature of the `RsSgt` is **Instrument Status Checking**. Check out the next chapter that describes the error checking in details.

For completion, we mention other string-based `write_xxx()` and `query_xxx()` methods - all in one example. They are convenient extensions providing type-safe float/boolean/integer setting/querying features:

```
"""
Basic string write_xxx / query_xxx
"""

from RsSgt import *

driver = RsSgt('TCPIP::192.168.56.101::INSTR')
driver.utilities.visa_timeout = 5000
driver.utilities.instrument_status_checking = True
driver.utilities.write_int('SWEEP:COUNT ', 10) # sending 'SWEEP:COUNT 10'
driver.utilities.write_bool('SOURCE:RF:OUTPUT:STATE ', True) # sending
↳ 'SOURCE:RF:OUTPUT:STATE ON'
driver.utilities.write_float('SOURCE:RF:FREQUENCY ', 1E9) # sending 'SOURCE:RF:FREQUENCY_
↳ 1000000000'

sc = driver.utilities.query_int('SWEEP:COUNT?') # returning integer number sc=10
out = driver.utilities.query_bool('SOURCE:RF:OUTPUT:STATE?') # returning boolean_
↳ out=True
freq = driver.utilities.query_float('SOURCE:RF:FREQUENCY?') # returning float number_
↳ freq=1E9

# Close the session
driver.close()
```

Lastly, a method providing basic synchronization: `query_opc()`. It sends query `*OPC?` to your instrument. The instrument waits with the answer until all the tasks it currently has in a queue are finished. This way your program waits too, and this way it is synchronized with the actions in the instrument. Remember to have the VISA timeout set to an appropriate value to prevent the timeout exception. Here's the snippet:

```
driver.utilities.visa_timeout = 3000
driver.utilities.write_str("INIT")
driver.utilities.query_opc()

# The results are ready now to fetch
results = driver.utilities.query_str("FETCH:MEASUREMENT?")
```

**Tip:** Wait, there's more: you can send the `*OPC?` after each `write_xxx()` automatically:

```
# Default value after init is False
driver.utilities.opc_query_after_write = True
```

## 2.6 Error Checking

RsSgt pushes limits even further (internal R&S joke): It has a built-in mechanism that after each command/query checks the instrument's status subsystem, and raises an exception if it detects an error. For those who are already screaming: **Speed Performance Penalty!!!**, don't worry, you can disable it.

Instrument status checking is very useful since in case your command/query caused an error, you are immediately informed about it. Status checking has in most cases no practical effect on the speed performance of your program. However, if for example, you do many repetitions of short write/query sequences, it might make a difference to switch it off:

```
# Default value after init is True
driver.utilities.instrument_status_checking = False
```

To clear the instrument status subsystem of all errors, call this method:

```
driver.utilities.clear_status()
```

Instrument's status system error queue is clear-on-read. It means, if you query its content, you clear it at the same time. To query and clear list of all the current errors, use this snippet:

```
errors_list = driver.utilities.query_all_errors()
```

See the next chapter on how to react on errors.

## 2.7 Exception Handling

The base class for all the exceptions raised by the RsSgt is `RsInstrException`. Inherited exception classes:

- `ResourceError` raised in the constructor by problems with initiating the instrument, for example wrong or non-existing resource name
- `StatusException` raised if a command or a query generated error in the instrument's error queue
- `TimeoutException` raised if a visa timeout or an opc timeout is reached

In this example we show usage of all of them. Because it is difficult to generate an error using the instrument-specific SCPI API, we use plain SCPI commands:

```
"""
Showing how to deal with exceptions
"""

from RsSgt import *

driver = None
# Try-catch for initialization. If an error occurs, the ResourceError is raised
try:
    driver = RsSgt('TCPIP::10.112.1.179::hislip0')
except ResourceError as e:
    print(e.args[0])
    print('Your instrument is probably OFF...')
    # Exit now, no point of continuing
    exit(1)
```

(continues on next page)

(continued from previous page)

```

# Dealing with commands that potentially generate errors OPTION 1:
# Switching the status checking OFF temporarily
driver.utilities.instrument_status_checking = False
driver.utilities.write_str('MY:MISSpelled:COMMAND')
# Clear the error queue
driver.utilities.clear_status()
# Status checking ON again
driver.utilities.instrument_status_checking = True

# Dealing with queries that potentially generate errors OPTION 2:
try:
    # You might want to reduce the VISA timeout to avoid long waiting
    driver.utilities.visa_timeout = 1000
    driver.utilities.query_str('MY:WRONG:QUERy?')

except StatusException as e:
    # Instrument status error
    print(e.args[0])
    print('Nothing to see here, moving on...')

except TimeoutException as e:
    # Timeout error
    print(e.args[0])
    print('That took a long time...')

except RsInstrException as e:
    # RsInstrException is a base class for all the RsSgt exceptions
    print(e.args[0])
    print('Some other RsSgt error...')

finally:
    driver.utilities.visa_timeout = 5000
    # Close the session in any case
    driver.close()

```

**Tip:** General rules for exception handling:

- If you are sending commands that might generate errors in the instrument, for example deleting a file which does not exist, use the **OPTION 1** - temporarily disable status checking, send the command, clear the error queue and enable the status checking again.
- If you are sending queries that might generate errors or timeouts, for example querying measurement that can not be performed at the moment, use the **OPTION 2** - try/except with optionally adjusting the timeouts.

## 2.8 Transferring Files

### Instrument -> PC

You definitely experienced it: you just did a perfect measurement, saved the results as a screenshot to an instrument's storage drive. Now you want to transfer it to your PC. With RsSgt, no problem, just figure out where the screenshot was stored on the instrument. In our case, it is `/var/user/instr_screenshot.png`:

```
driver.utilities.read_file_from_instrument_to_pc(  
    r'/var/user/instr_screenshot.png',  
    r'c:\temp\pc_screenshot.png')
```

### PC -> Instrument

Another common scenario: Your cool test program contains a setup file you want to transfer to your instrument: Here is the RsSgt one-liner split into 3 lines:

```
driver.utilities.send_file_from_pc_to_instrument(  
    r'c:\MyCoolTestProgram\instr_setup.sav',  
    r'/var/appdata/instr_setup.sav')
```

## 2.9 Writing Binary Data

### Writing from bytes

An example where you need to send binary data is a waveform file of a vector signal generator. First, you compose your `wform_data` as bytes, and then you send it with `write_bin_block()`:

```
# MyWaveform.wv is an instrument file name under which this data is stored  
driver.utilities.write_bin_block(  
    "SOUR:BB:ARB:WAV:DATA 'MyWaveform.wv'",  
    wform_data)
```

---

**Note:** Notice the `write_bin_block()` has two parameters:

- string parameter `cmd` for the SCPI command
  - bytes parameter `payload` for the actual binary data to send
- 

### Writing from PC files

Similar to querying binary data to a file, you can write binary data from a file. The second parameter is then the PC file path the content of which you want to send:

```
driver.utilities.write_bin_block_from_file(  
    "SOUR:BB:ARB:WAV:DATA 'MyWaveform.wv'",  
    r"c:\temp\wform_data.wv")
```

## 2.10 Transferring Big Data with Progress

We can agree that it can be annoying using an application that shows no progress for long-lasting operations. The same is true for remote-control programs. Luckily, the RsSgt has this covered. And, this feature is quite universal - not just for big files transfer, but for any data in both directions.

RsSgt allows you to register a function (programmers fancy name is `callback`), which is then periodically invoked after transfer of one data chunk. You can define that chunk size, which gives you control over the callback invoke frequency. You can even slow down the transfer speed, if you want to process the data as they arrive (direction instrument -> PC).

To show this in praxis, we are going to use another *University-Professor-Example*: querying the `*IDN?` with chunk size of 2 bytes and delay of 200ms between each chunk read:

```
"""
Event handlers by reading
"""

from RsSgt import *
import time

def my_transfer_handler(args):
    """Function called each time a chunk of data is transferred"""
    # Total size is not always known at the beginning of the transfer
    total_size = args.total_size if args.total_size is not None else "unknown"

    print(f"Context: '{args.context}'{'with opc' if args.opc_sync else ''}', "
          f"chunk {args.chunk_ix}, "
          f"transferred {args.transferred_size} bytes, "
          f"total size {total_size}, "
          f"direction {'reading' if args.reading else 'writing'}, "
          f"data '{args.data}'")

    if args.end_of_transfer:
        print('End of Transfer')
        time.sleep(0.2)

driver = RsSgt('TCPIP::192.168.56.101::INSTR')

driver.events.on_read_handler = my_transfer_handler
# Switch on the data to be included in the event arguments
# The event arguments args.data will be updated
driver.events.io_events_include_data = True
# Set data chunk size to 2 bytes
driver.utilities.data_chunk_size = 2
driver.utilities.query_str('*IDN?')
# Unregister the event handler
driver.utilities.on_read_handler = None

# Close the session
driver.close()
```

If you start it, you might wonder (or maybe not): why is the `args.total_size = None`? The reason is, in this

particular case the RsSgt does not know the size of the complete response up-front. However, if you use the same mechanism for transfer of a known data size (for example, file transfer), you get the information about the total size too, and hence you can calculate the progress as:

$$progress [pct] = 100 * args.transferred\_size / args.total\_size$$

Snippet of transferring file from PC to instrument, the rest of the code is the same as in the previous example:

```
driver.events.on_write_handler = my_transfer_handler
driver.events.io_events_include_data = True
driver.data_chunk_size = 1000
driver.utilities.send_file_from_pc_to_instrument(
    r'c:\MyCoolTestProgram\my_big_file.bin',
    r'/var/user/my_big_file.bin')
# Unregister the event handler
driver.events.on_write_handler = None
```

## 2.11 Multithreading

You are at the party, many people talking over each other. Not every person can deal with such crosstalk, neither can measurement instruments. For this reason, RsSgt has a feature of scheduling the access to your instrument by using so-called **Locks**. Locks make sure that there can be just one client at a time *talking* to your instrument. Talking in this context means completing one communication step - one command write or write/read or write/read/error check.

To describe how it works, and where it matters, we take three typical multithread scenarios:

### One instrument session, accessed from multiple threads

You are all set - the lock is a part of your instrument session. Check out the following example - it will execute properly, although the instrument gets 10 queries at the same time:

```
"""
Multiple threads are accessing one RsSgt object
"""

import threading
from RsSgt import *

def execute(session):
    """Executed in a separate thread."""
    session.utilities.query_str('*IDN?')

driver = RsSgt('TCPIP::192.168.56.101::INSTR')
threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver, ))
    t.start()
    threads.append(t)
print('All threads started')
```

(continues on next page)



(continued from previous page)

```

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

driver.close()

```

### Shared instrument session, accessed from multiple threads

Same as the previous case, you are all set. The session carries the lock with it. You have two objects, talking to the same instrument from multiple threads. Since the instrument session is shared, the same lock applies to both objects causing the exclusive access to the instrument.

Try the following example:

```

"""
Multiple threads are accessing two RsSgt objects with shared session
"""

import threading
from RsSgt import *

def execute(session: RsSgt, session_ix, index) -> None:
    """Executed in a separate thread."""
    print(f'{index} session {session_ix} query start...')
    session.utilities.query_str('*IDN?')
    print(f'{index} session {session_ix} query end')

driver1 = RsSgt('TCPIP::192.168.56.101::INSTR')
driver2 = RsSgt.from_existing_session(driver1)
driver1.utilities.visa_timeout = 200
driver2.utilities.visa_timeout = 200
# To see the effect of crosstalk, uncomment this line
# driver2.utilities.clear_lock()

threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver1, 1, i))
    t.start()
    threads.append(t)
    t = threading.Thread(target=execute, args=(driver2, 2, i))
    t.start()
    threads.append(t)
print('All threads started')

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

```

(continues on next page)

(continued from previous page)

```
driver2.close()
driver1.close()
```

As you see, everything works fine. If you want to simulate some party crosstalk, uncomment the line `driver2.utilities.clear_lock()`. This causes the driver2 session lock to break away from the driver1 session lock. Although the driver1 still tries to schedule its instrument access, the driver2 tries to do the same at the same time, which leads to all the fun stuff happening.

## Multiple instrument sessions accessed from multiple threads

Here, there are two possible scenarios depending on the instrument's VISA interface:

- You are lucky, because your instrument handles each remote session completely separately. An example of such instrument is SMW200A. In this case, you have no need for session locking.
- Your instrument handles all sessions with one set of in/out buffers. You need to lock the session for the duration of a talk. And you are lucky again, because the RsSgt takes care of it for you. The text below describes this scenario.

Run the following example:

```
"""
Multiple threads are accessing two RsSgt objects with two separate sessions
"""

import threading
from RsSgt import *

def execute(session: RsSgt, session_ix, index) -> None:
    """Executed in a separate thread."""
    print(f'{index} session {session_ix} query start...')
    session.utilities.query_str('*IDN?')
    print(f'{index} session {session_ix} query end')

driver1 = RsSgt('TCPIP::192.168.56.101::INSTR')
driver2 = RsSgt('TCPIP::192.168.56.101::INSTR')
driver1.utilities.visa_timeout = 200
driver2.utilities.visa_timeout = 200

# Synchronise the sessions by sharing the same lock
driver2.utilities.assign_lock(driver1.utilities.get_lock()) # To see the effect of
↳ crosstalk, comment this line

threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver1, 1, i,))
    t.start()
    threads.append(t)
    t = threading.Thread(target=execute, args=(driver2, 2, i,))
    t.start()
```

(continues on next page)

(continued from previous page)

```

        threads.append(t)
print('All threads started')

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

driver2.close()
driver1.close()

```

You have two completely independent sessions that want to talk to the same instrument at the same time. This will not go well, unless they share the same session lock. The key command to achieve this is `driver2.utilities.assign_lock(driver1.utilities.get_lock())`. Try to comment it and see how it goes. If despite commenting the line the example runs without issues, you are lucky to have an instrument similar to the SMW200A.

## 2.12 Logging

Yes, the logging again. This one is tailored for instrument communication. You will appreciate such handy feature when you troubleshoot your program, or just want to protocol the SCPI communication for your test reports.

What can you actually do with the logger?

- Write SCPI communication to a stream-like object, for example console or file, or both simultaneously
- Log only errors and skip problem-free parts; this way you avoid going through thousands lines of texts
- Investigate duration of certain operations to optimize your program's performance
- Log custom messages from your program

Let us take this basic example:

```

"""
Basic logging example to the console
"""

from RsSgt import *

driver = RsSgt('TCPIP::192.168.1.101::INSTR')

# Switch ON logging to the console.
driver.utilities.logger.log_to_console = True
driver.utilities.logger.mode = LoggingMode.On
driver.utilities.reset()

# Close the session
driver.close()

```

Console output:

```

10:29:10.819    TCPIP::192.168.1.101::INSTR    0.976 ms  Write: *RST
10:29:10.819    TCPIP::192.168.1.101::INSTR  1884.985 ms  Status check: OK
10:29:12.704    TCPIP::192.168.1.101::INSTR    0.983 ms  Query OPC: 1

```

(continues on next page)

(continued from previous page)

10:29:12.705	TCPIP::192.168.1.101::INSTR	2.892 ms	Clear status: OK
10:29:12.708	TCPIP::192.168.1.101::INSTR	3.905 ms	Status check: OK
10:29:12.712	TCPIP::192.168.1.101::INSTR	1.952 ms	Close: Closing session

The columns of the log are aligned for better reading. Columns meaning:

- (1) Start time of the operation
- (2) Device resource name (you can set an alias)
- (3) Duration of the operation
- (4) Log entry

**Tip:** You can customize the logging format with `set_format_string()`, and set the maximum log entry length with the properties:

- `abbreviated_max_len_ascii`
- `abbreviated_max_len_bin`
- `abbreviated_max_len_list`

See the full logger help [here](#).

Notice the SCPI communication starts from the line `driver.utilities.reset()`. If you want to log the initialization of the session as well, you have to switch the logging ON already in the constructor:

```
driver = RsSgt('TCPIP::192.168.56.101::hislip0', options='LoggingMode=On')
```

Parallel to the console logging, you can log to a general stream. Do not fear the programmer's jargon... under the term **stream** you can just imagine a file. To be a little more technical, a stream in Python is any object that has two methods: `write()` and `flush()`. This example opens a file and sets it as logging target:

```
"""
Example of logging to a file
"""

from RsSgt import *

driver = RsSgt('TCPIP::192.168.1.101::INSTR')

# We also want to log to the console.
driver.utilities.logger.log_to_console = True

# Logging target is our file
file = open(r'c:\temp\my_file.txt', 'w')
driver.utilities.logger.set_logging_target(file)
driver.utilities.logger.mode = LoggingMode.On

# Instead of the 'TCPIP::192.168.1.101::INSTR', show 'MyDevice'
driver.utilities.logger.device_name = 'MyDevice'

# Custom user entry
driver.utilities.logger.info_raw('----- This is my custom log entry. ---- ')
```

(continues on next page)

(continued from previous page)

```
driver.utilities.reset()

# Close the session
driver.close()

# Close the log file
file.close()
```

**Tip:** To make the log more compact, you can skip all the lines with Status check: OK:

```
driver.utilities.logger.log_status_check_ok = False
```

**Hint:** You can share the logging file between multiple sessions. In such case, remember to close the file only after you have stopped logging in all your sessions, otherwise you get a log write error.

For logging to a UDP port in addition to other log targets, use one of the lines:

```
driver.utilities.logger.log_to_udp = True
driver.utilities.logger.log_to_console_and_udp = True
```

You can select the UDP port to log to, the default is 49200:

```
driver.utilities.logger.udp_port = 49200
```

Another cool feature is logging only errors. To make this mode useful for troubleshooting, you also want to see the circumstances which lead to the errors. Each driver elementary operation, for example, `write_str()`, can generate a group of log entries - let us call them **Segment**. In the logging mode **Errors**, a whole segment is logged only if at least one entry of the segment is an error.

The script below demonstrates this feature. We use a direct SCPI communication to send a misspelled SCPI command `*CLS`, which leads to instrument status error:

```
"""
Logging example to the console with only errors logged
"""

from RsSgt import *

driver = RsSgt('TCPIP::192.168.1.101::INSTR', options='LoggingMode=Errors')

# Switch ON logging to the console.
driver.utilities.logger.log_to_console = True

# Reset will not be logged, since no error occurred there
driver.utilities.reset()

# Now a misspelled command.
driver.utilities.write('*CLaS')
```

(continues on next page)

(continued from previous page)

```
# A good command again, no logging here
idn = driver.utilities.query('*IDN?')

# Close the session
driver.close()
```

Console output:

```
12:11:02.879 TCP/IP::192.168.1.101::INSTR    0.976 ms  Write string: *CLaS
12:11:02.879 TCP/IP::192.168.1.101::INSTR    6.833 ms  Status check: StatusException:
                                           Instrument error detected: Undefined header;
↪ *CLaS
```

Notice the following:

- Although the operation **Write string: \*CLaS** finished without an error, it is still logged, because it provides the context for the actual error which occurred during the status checking right after.
- No other log entries are present, including the session initialization and close, because they were all error-free.

### 3.1 AttMode

```
# Example value:  
value = enums.AttMode.APASSive  
# All values (3x):  
APASSive | AUTO | FIXed
```

### 3.2 BbSystemConfiguration

```
# Example value:  
value = enums.BbSystemConfiguration.AFETracking  
# All values (2x):  
AFETracking | STANdard
```

### 3.3 CalPowDetAtt

```
# Example value:  
value = enums.CalPowDetAtt.HIGH  
# All values (4x):  
HIGH | LOW | MED | OFF
```

### 3.4 FreqStepMode

```
# Example value:  
value = enums.FreqStepMode.DECimal  
# All values (2x):  
DECimal | USER
```

## 3.5 ImpG50G10K

```
# Example value:  
value = enums.ImpG50G10K.G10K  
# All values (2x):  
G10K | G50
```

## 3.6 InclExcl

```
# Example value:  
value = enums.InclExcl.EXCLude  
# All values (2x):  
EXCLude | INCLUDE
```

## 3.7 InputImpRf

```
# Example value:  
value = enums.InputImpRf.G10K  
# All values (3x):  
G10K | G1K | G50
```

## 3.8 IqMode

```
# Example value:  
value = enums.IqMode.ANALog  
# All values (2x):  
ANALog | BASeband
```

## 3.9 OpMode

```
# Example value:  
value = enums.OpMode.BBBYpass  
# All values (2x):  
BBBYpass | NORMa1
```



## 3.10 PowAlcState

```
# Example value:  
value = enums.PowAlcState._1  
# All values (4x):  
_1 | AUTO | OFF | ON
```

## 3.11 PowLevBehaviour

```
# Example value:  
value = enums.PowLevBehaviour.AUTO  
# All values (6x):  
AUTO | CVSWr | CWSWr | MONotone | UNINterrupted | USER
```

## 3.12 PowLevMode

```
# Example value:  
value = enums.PowLevMode.LOWDistortion  
# All values (4x):  
LOWDistortion | LOWNoise | NORMal | USER
```

## 3.13 PowOutPonMode

```
# Example value:  
value = enums.PowOutPonMode.OFF  
# All values (2x):  
OFF | UNCHanged
```

## 3.14 PowRfOffMode

```
# Example value:  
value = enums.PowRfOffMode.FIXed  
# All values (2x):  
FIXed | MAX
```

## 3.15 PowSensWithUndef

```
# First value:  
value = enums.PowSensWithUndef.SENS1  
# Last value:  
value = enums.PowSensWithUndef.UNDEFINED  
# All values (9x):  
SENS1 | SENS2 | SENS3 | SENS4 | SENSor1 | SENSor2 | SENSor3 | SENSor4  
UNDEFINED
```

## 3.16 RefLoOutput

```
# Example value:  
value = enums.RefLoOutput.LO  
# All values (3x):  
LO | OFF | REF
```

## 3.17 RoscFreqExt

```
# Example value:  
value = enums.RoscFreqExt._1000MHZ  
# All values (4x):  
_1000MHZ | _100MHZ | _10MHZ | _13MHZ
```

## 3.18 SlopeType

```
# Example value:  
value = enums.SlopeType.NEGative  
# All values (2x):  
NEGative | POSitive
```

## 3.19 SourceInt

```
# Example value:  
value = enums.SourceInt.EXternal  
# All values (2x):  
EXternal | Internal
```

## 3.20 Test

```
# Example value:
value = enums.Test._0
# All values (4x):
_0 | _1 | RUNning | STOPped
```

## 3.21 UserPlug

```
# First value:
value = enums.UserPlug.CIN
# Last value:
value = enums.UserPlug.TRIGger
# All values (18x):
CIN | COUT | HIGH | LOW | MARRived | MKR1 | MKR2 | MLATency
NEXT | PEMSource | PETRigger | PVOut | SIN | SNValid | SOUT | SVALid
TOUT | TRIGger
```



## REPCAPS

## 4.1 HwInstance (Global)

```
# Setting:
driver.repcap_hwInstance_set(repcap.HwInstance.InstA)
# Range:
InstA .. InstH
# All values (8x):
InstA | InstB | InstC | InstD | InstE | InstF | InstG | InstH
```

## 4.2 BitNumberNull

```
# First value:
value = repcap.BitNumberNull.Nr0
# Range:
Nr0 .. Nr15
# All values (16x):
Nr0 | Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7
Nr8 | Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15
```

## 4.3 IqConnector

```
# First value:
value = repcap.IqConnector.Nr1
# Values (4x):
Nr1 | Nr2 | Nr3 | Nr4
```

## 4.4 UserIx

```
# First value:
value = repcap.UserIx.Nr1
# Range:
Nr1 .. Nr48
# All values (48x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
Nr17 | Nr18 | Nr19 | Nr20 | Nr21 | Nr22 | Nr23 | Nr24
Nr25 | Nr26 | Nr27 | Nr28 | Nr29 | Nr30 | Nr31 | Nr32
Nr33 | Nr34 | Nr35 | Nr36 | Nr37 | Nr38 | Nr39 | Nr40
Nr41 | Nr42 | Nr43 | Nr44 | Nr45 | Nr46 | Nr47 | Nr48
```

## EXAMPLES

For more examples, visit our Rohde & Schwarz Github repository.

```
"""Getting started - how to work with RsSgt Python package.
This example performs basic RF settings on an SGT100A instrument.
It shows the RsSgt calls and their corresponding SCPI commands.
Notice that the python RsSgt interfaces track the SCPI commands syntax."""
```

```
from RsSgt import *

# Open the session
sgt = RsSgt('TCPIP::10.112.0.228::HISLIP')
# Greetings, stranger...
print(f'Hello, I am: {sgt.utilities.idn_string}')

#  OUTPut:STATe ON
sgt.output.state.set_value(True)

#  SOURce:POWer:LEVel:IMMediate:AMPLitude -25
sgt.source.power.level.immediate.set_amplitude(-25)

#  SOURce:FREQuency:FIXed 11000000000
sgt.source.frequency.fixed.set_value(1.1E9)

#          SOURce:POWer:PEP?
pep = sgt.source.power.get_pep()
print(f'PEP level: {pep} dBm')

# Close the session
sgt.close()
```

```
"""Basic example of importing the package, initializing the session and performing basic
↪ generator settings."""
```

```
from RsSgt import *

sgt = RsSgt('TCPIP::10.112.1.73::HISLIP')
# sgt = RsSgt('TCPIP::10.214.1.57::5025::SOCKET', options='SelectVisa=SocketIo') # No VISA
↪ needed
print(f'Driver Info: {sgt.utilities.driver_version}')
```

(continues on next page)

(continued from previous page)

```

print(f'Instrument: {sgt.utilities.idn_string}')

# Instrument options are properly parsed, and sorted (k-options first)
print(f'Instrument options: {"", ".join(sgt.utilities.instrument_options)}')

# Driver's instrument status checking ( SYST:ERR? ) after each command (default value is
↳ True):
sgt.utilities.instrument_status_checking = True

sgt.output.state.set_value(True)
sgt.source.power.level.immediate.set_amplitude(-20)
sgt.source.frequency.fixed.set_value(223E6)
print(f'PEP level: {sgt.source.power.get_pep()} dBm')

# You can still use the direct SCPI interface:
response = sgt.utilities.query_str('*IDN?')
print(f'Direct SCPI response on *IDN?: {response}')
sgt.close()

```

```

"""The example:
- creates waveform file from a csv-file with I/Q pairs
- sends the file to the SGT100A instrument
- activates the waveform
You have the option of auto-scaling the samples to the full range with the parameter
↳ 'auto_scale'
"""

```

```

import numpy as np
from RsSgt import *

RsSgt.assert_minimum_version('4.70.1')
sgt = RsSgt('TCPIP::10.214.1.57::HISLIP')
print(sgt.utilities.idn_string)
sgt.utilities.reset()

pc_csv_file = r'c:\temp\arbFileExample.csv'
pc_wv_file = r'c:\temp\arbFileExample.wv'
instr_wv_file = '/var/user/InstrDemoFile.wv'

# Skip this part if you have a csv-file available

# Samples clock
clock_freq = 600e6
# wave clock
wave_freq = 120e6
# Scale factor - change it to less or more than 1 if you want to see the autoscaling
↳ capability of the create_waveform_file...() methods
scale_factor = 0.43
time_vector = np.arange(0, 50 / wave_freq, 1 / clock_freq)
# I-component and Q-component data
i_data = np.cos(2 * np.pi * wave_freq * time_vector) * scale_factor
q_data = np.sin(2 * np.pi * wave_freq * time_vector) * scale_factor

```

(continues on next page)



(continued from previous page)

```

with open(pc_csv_file, 'w') as file:
    for x in range(len(i_data)):
        file.write(f'{i_data[x]}, {q_data[x]}\n')

# Take that csv-file with the IQ-samples and create a wav file
result = sgt.arb_files.create_waveform_file_from_samples_file(pc_csv_file, pc_wv_file,
    ↪ clock_freq=100E6, auto_scale=False, comment='Created from a csv file')
print(result)

# Send to the instrument
sgt.arb_files.send_waveform_file_to_instrument(pc_wv_file, instr_wv_file)

# Selecting the waveform and load it in ARB
sgt.source.bb.arbitrary.waveform.set_select(instr_wv_file)

# Turning on the ARB baseband
sgt.source.bb.arbitrary.set_state(True)

# Turning on the RF output state
sgt.output.state.set_value(True)

sgt.close()

```

```

"""The example:
- creates waveform file from two i_data and q_data vectors
- sends the file to the SGT100A instrument
- activates the waveform
You have the option of auto-scaling the samples to the full range with the parameter
↪ 'auto_scale'
"""

```

```

import numpy as np
from RsSgt import *

RsSgt.assert_minimum_version('4.70.1')
sgt = RsSgt('TCPIP::10.214.1.57::HISLIP')
print(sgt.utilities.idn_string)
sgt.utilities.reset()

pc_wv_file = r'c:\temp\arbFileExample.wv'
instr_wv_file = '/var/user/InstrDemoFile.wv'

# Creating the I/Q vectors as lists: i_data / q_data
# Samples clock
clock_freq = 600e6
# wave clock
wave_freq = 120e6
# Scale factor - change it to less or more than 1 if you want to see the autoscaling_
    ↪ capability of the create_waveform_file...() methods
scale_factor = 0.8
time_vector = np.arange(0, 50 / wave_freq, 1 / clock_freq)

```

(continues on next page)

(continued from previous page)

```

# I-component an Q-component data
i_data = np.cos(2 * np.pi * wave_freq * time_vector) * scale_factor
q_data = np.sin(2 * np.pi * wave_freq * time_vector) * scale_factor

# Take those samples and create a wav file, send it to the instrument with the name instr_
↳wav_file (not auto-scaled)
result = sgt.arb_files.create_waveform_file_from_samples(i_data, q_data, pc_wv_file,
↳clock_freq=100E6, auto_scale=False, comment='Created from I/Q vectors')
sgt.arb_files.send_waveform_file_to_instrument(pc_wv_file, instr_wv_file)

# Selecting the waveform and load it in the ARB
sgt.source.bb.arbitrary.waveform.set_select(instr_wv_file)
sgt.source.frequency.fixed.set_value(1.1E9)
sgt.source.power.level.immediate.set_amplitude(-11.1)
# Turning on the ARB baseband
sgt.source.bb.arbitrary.set_state(True)
# Turning on the RF out state
sgt.output.state.set_value(True)

sgt.close()

```

```

"""Example showing how you can transfer a big file to the instrument and from the
↳instrument with showing the progress.
Since the SGT100A is quite fast on data transfer, we slow it down by waiting for 100ms
↳between each chunk transfer (1MB)
This way we see the transfer progress better and we do not need a file that is so big -
↳let's take cca 20MB.
For big files, use the example without the time.sleep(0.1)"""

```

```

import time
import numpy as np
from RsSgt import *

def my_transfer_handler(args):
    """Function called each time a chunk of data is transferred"""
    total_size = args.total_size if args.total_size is not None else "unknown"
    print(f"Context: '{args.context}{'with opc' if args.opc_sync else ''}', "
          f"chunk {args.chunk_ix}, "
          f"transferred {args.transferred_size} bytes, "
          f"total size {total_size}, "
          f"direction {'reading' if args.reading else 'writing'}, "
          f"data '{args.data}'")
    if args.end_of_transfer:
        print('End of Transfer')
    # Slow down the transfer by 200ms to see the progress better
    time.sleep(0.1)

sgt = RsSgt('TCPIP::10.214.1.57::HISLIP')
print(sgt.utilities.idn_string)
sgt.utilities.reset()

```

(continues on next page)

(continued from previous page)

```
pc_file = r'c:\temp\bigFile.bin'
instr_file = '/var/user/bigFileInstr.bin'
pc_file_back = r'c:\temp\bigFileBack.bin'

# Generate a random file of 20MB size
x1mb = 1024 * 1024
with open(pc_file, 'wb') as file:
    for x in range(20):
        file.write(np.random.bytes(x1mb))

# Send the file to the instrument with events
sgt.events.on_write_handler = my_transfer_handler
sgt.utilities.data_chunk_size = x1mb
print(f'Sending file to the instrument...')
sgt.utilities.send_file_from_pc_to_instrument(pc_file, instr_file)
sgt.events.on_write_handler = None
print(f'Receiving file from the instrument...')
sgt.events.on_read_handler = my_transfer_handler
sgt.utilities.read_file_from_instrument_to_pc(instr_file, pc_file_back)
sgt.events.on_read_handler = None
sgt.close()
```



## RSSGT API STRUCTURE

### Global RepCaps

```
driver = RsSgt('TCPIP::192.168.2.101::hislip0')
# HwInstance range: InstA .. InstH
rc = driver.repcap_hwInstance_get()
driver.repcap_hwInstance_set(repcap.HwInstance.InstA)
```

**class RsSgt**(resource\_name: str, id\_query: bool = True, reset: bool = False, options: str = None, direct\_session: object = None)

176 total commands, 10 Subgroups, 4 group commands

Initializes new RsSgt session.

#### Parameter options tokens examples:

- Simulate=True - starts the session in simulation mode. Default: False
- SelectVisa=socket - uses no VISA implementation for socket connections - you do not need any VISA-C installation
- SelectVisa=rs - forces usage of RohdeSchwarz Visa
- SelectVisa=ivi - forces usage of National Instruments Visa
- QueryInstrumentStatus = False - same as driver.utilities.instrument\_status\_checking = False. Default: True
- WriteDelay = 20, ReadDelay = 5 - Introduces delay of 20ms before each write and 5ms before each read. Default: 0ms for both
- OpcWaitMode = OpcQuery - mode for all the opc-synchronised write/reads. Other modes: StbPolling, StbPollingSlow, StbPollingSuperSlow. Default: StbPolling
- AddTermCharToWriteBinBlock = True - Adds one additional LF to the end of the binary data (some instruments require that). Default: False
- AssureWriteWithTermChar = True - Makes sure each command/query is terminated with termination character. Default: Interface dependent
- TerminationCharacter = "\r" - Sets the termination character for reading. Default: \n (LineFeed or LF)
- DataChunkSize = 10E3 - Maximum size of one write/read segment. If transferred data is bigger, it is split to more segments. Default: 1E6 bytes
- OpcTimeout = 10000 - same as driver.utilities.opc\_timeout = 10000. Default: 30000ms
- VisaTimeout = 5000 - same as driver.utilities.visa\_timeout = 5000. Default: 10000ms

- `ViClearExeMode = Disabled` - `viClear()` execution mode. Default: `execute_on_all`
- `OpcQueryAfterWrite = True` - same as `driver.utilities.opc_query_after_write = True`. Default: `False`
- `StbInErrorCheck = False` - if true, the driver checks errors with `*STB?` If false, it uses `SYST:ERR?`. Default: `True`
- `ScpiQuotes = double'` - for SCPI commands, you can define how strings are quoted. With single or double quotes. Possible values: `single` | `double` | `{char}`. Default: ```single`
- `LoggingMode = On` - Sets the logging status right from the start. Default: `Off`
- `LoggingName = 'MyDevice'` - Sets the name to represent the session in the log entries. Default: `'resource_name'`
- `LogToGlobalTarget = True` - Sets the logging target to the class-property previously set with `RsSgt.set_global_logging_target()` Default: `False`
- `LoggingToConsole = True` - Immediately starts logging to the console. Default: `False`
- `LoggingToUdp = True` - Immediately starts logging to the UDP port. Default: `False`
- `LoggingUdpPort = 49200` - UDP port to log to. Default: `49200`

#### Parameters

- **resource\_name** – VISA resource name, e.g. `'TCPIP::192.168.2.1::INSTR'`
- **id\_query** – if `True`, the instrument's model name is verified against the models supported by the driver and eventually throws an exception.
- **reset** – Resets the instrument (sends `*RST` command) and clears its status subsystem.
- **options** – string tokens alternating the driver settings.
- **direct\_session** – Another driver object or `pyVisa` object to reuse the session instead of opening a new session.

#### class LockStruct

Structure for reading output parameters. Fields:

- `Lock_Request_Id`: float: Number 0 test query to prove whether the instrument is locked Controller ID request lock from the controller with the specified Controller ID
- `Value`: float: Number 0 request refused; the instrument is already locked to other Lock Request Id, i.e. to another controller 1 request granted

#### static assert\_minimum\_version(min\_version: str) → None

Asserts that the driver version fulfills the minimum required version you have entered. This way you make sure your installed driver is of the entered version or newer.

#### classmethod clear\_global\_logging\_relative\_timestamp() → None

Clears the global relative timestamp. After this, all the instances using the global relative timestamp continue logging with the absolute timestamps.

#### close() → None

Closes the active RsSgt session.

#### classmethod from\_existing\_session(session: object, options: str = None) → RsSgt

Creates a new RsSgt object with the entered 'session' reused.

#### Parameters

- **session** – can be another driver or a direct pyvisa session.
- **options** – string tokens alternating the driver settings.

**get\_ffast()** → float

```
# SCPI: FFAST
value: float = driver.get_ffast()
```

Special command to set the RF output frequency with minimum latency. No unit (e.g. Hz) allowed. Bypasses the status system so command *\*OPC?* cannot be appended.

**return**  
freq: float

**classmethod get\_global\_logging\_relative\_timestamp()** → datetime

Returns global common relative timestamp for log entries.

**classmethod get\_global\_logging\_target()**

Returns global common target stream.

**get\_lock()** → LockStruct

```
# SCPI: LOCK
value: LockStruct = driver.get_lock()
```

Sends a lock request ID which uniquely identifies the controller to the instrument.

**return**  
structure: for return value, see the help for LockStruct structure arguments.

**get\_pfast()** → float

```
# SCPI: PFAST
value: float = driver.get_pfast()
```

Special command to set the RF output level with minimum latency at the RF output connector. This value does not consider a specified offset. No unit (e.g. dBm) allowed. Bypasses the status system so command *\*OPC?* cannot be appended.

**return**  
power: float

**get\_session\_handle()** → object

Returns the underlying session handle.

**get\_total\_execution\_time()** → timedelta

Returns total time spent by the library on communicating with the instrument. This time is always shorter than `get_total_time()`, since it does not include gaps between the communication. You can reset this counter with `reset_time_statistics()`.

**get\_total\_time()** → timedelta

Returns total time spent by the library on communicating with the instrument. This time is always shorter than `get_total_time()`, since it does not include gaps between the communication. You can reset this counter with `reset_time_statistics()`.

**static list\_resources(expression: str = '?\*::INSTR', visa\_select: str = None)** → List[str]

Finds all the resources defined by the expression

- ‘?’ - matches all the available instruments
- ‘USB::?’ - matches all the USB instruments
- ‘TCPIP::192?’ - matches all the LAN instruments with the IP address starting with 192

### Parameters

- **expression** – see the examples in the function
- **visa\_select** – optional parameter selecting a specific VISA. Examples: ‘@ivi’, ‘@rs’

**reset\_time\_statistics()** → None

Resets all execution and total time counters. Affects the results of `get_total_time()` and `get_total_execution_time()`

**restore\_all\_repcaps\_to\_default()** → None

Sets all the Group and Global repcaps to their initial values

**set\_ffast(freq: float)** → None

```
# SCPI: FFASt
driver.set_ffast(freq = 1.0)
```

Special command to set the RF output frequency with minimum latency. No unit (e.g. Hz) allowed. Bypasses the status system so command \*OPC? cannot be appended.

**param freq**  
float

**classmethod set\_global\_logging\_relative\_timestamp(timestamp: datetime)** → None

Sets global common relative timestamp for log entries. To use it, call the following: `io.utilities.logger.set_relative_timestamp_global()`

**classmethod set\_global\_logging\_relative\_timestamp\_now()** → None

Sets global common relative timestamp for log entries to this moment. To use it, call the following: `io.utilities.logger.set_relative_timestamp_global()`.

**classmethod set\_global\_logging\_target(target)** → None

Sets global common target stream that each instance can use. To use it, call the following: `io.utilities.logger.set_logging_target_global()`. If an instance uses global logging target, it automatically uses the global relative timestamp (if set). You can set the target to None to invalidate it.

**set\_pfast(power: float)** → None

```
# SCPI: PFASt
driver.set_pfast(power = 1.0)
```

Special command to set the RF output level with minimum latency at the RF output connector. This value does not consider a specified offset. No unit (e.g. dBm) allowed. Bypasses the status system so command \*OPC? cannot be appended.

**param power**  
float

**unlock(unlock\_id: float)** → None

```
# SCPI: UNLock
driver.unlock(unlock_id = 1.0)
```



Unlocks an instrument locked to a controller with Controller ID = <Unlock Id>.

**param unlock\_id**

Number Unlock ID which uniquely identifies the controller to the instrument. The value must match the Controller ID Lock Request Id set with the command [CMDLINKRESOLVED #Lock CMDLINKRESOLVED]. 0 Clear lock regardless of locking state

## Subgroups

### 6.1 Calibration

**class CalibrationCls**

Calibration commands group definition. 10 total commands, 4 Subgroups, 0 group commands

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.clone()
```

## Subgroups

### 6.1.1 All

**SCPI Command :**

```
CALibration:ALL:[MEASure]
```

**class AllCls**

All commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_measure()** → bool

```
# SCPI: CALibration:ALL:[MEASure]
value: bool = driver.calibration.all.get_measure()
```

Starts all internal adjustments for which no external measuring equipment is required.

**return**

all\_py: 1| ON| 0| OFF

## 6.1.2 Frequency

### SCPI Commands :

```
CALibration:FREquency:TEMPerature
CALibration:FREquency:[MEASure]
```

#### class FrequencyCls

Frequency commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_measure()** → bool

```
# SCPI: CALibration:FREquency:[MEASure]
value: bool = driver.calibration.frequency.get_measure()
```

Performs all adjustments which affect the frequency.

```
return
    synthesis: 1| ON| 0| OFF
```

**get\_temperature()** → str

```
# SCPI: CALibration:FREquency:TEMPerature
value: str = driver.calibration.frequency.get_temperature()
```

Queries the delta temperature since the last performed adjustment.

```
return
    temperature: string
```

## 6.1.3 IqModulator

### SCPI Commands :

```
CALibration:IQModulator:FULL
CALibration:IQModulator:LOCal
CALibration:IQModulator:TEMPerature
```

#### class IqModulatorCls

IqModulator commands group definition. 5 total commands, 2 Subgroups, 3 group commands

**get\_full()** → bool

```
# SCPI: CALibration:IQModulator:FULL
value: bool = driver.calibration.iqModulator.get_full()
```

Starts the adjustment of the I/Q modulator for the entire frequency range. The I/Q modulator is adjusted with respect to carrier leakage, I/Q imbalance and quadrature.

```
return
    modulator: 1| ON| 0| OFF
```

**get\_local()** → bool

```
# SCPI: CALibration:IQModulator:LOCal
value: bool = driver.calibration.iqModulator.get_local()
```

Starts the adjustment of the I/Q modulator for the current frequency. The I/Q modulator is adjusted with respect to carrier leakage, I/Q imbalance and quadrature. This adjustment is only possible when OUT-Put[:STATe] ON and [:SOURce]:IQ:STATe ON.

```
return
cal_modulator_loc_error: No help available
```

**get\_temperature()** → str

```
# SCPI: CALibration:IQModulator:TEMPerature
value: str = driver.calibration.iqModulator.get_temperature()
```

Queries the delta temperature since the last performed adjustment.

```
return
temperature: string
```

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.iqModulator.clone()
```

## Subgroups

### 6.1.3.1 Bband

#### SCPI Command :

```
CALibration:IQModulator:BBAND:[STATe]
```

#### class BbandCls

Bband commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_state()** → bool

```
# SCPI: CALibration:IQModulator:BBAND:[STATe]
value: bool = driver.calibration.iqModulator.bband.get_state()
```

No command help available

```
return
modulator: OFF| ON| 1| 0
```

**set\_state(modulator: bool)** → None

```
# SCPI: CALibration:IQModulator:BBAND:[STATe]
driver.calibration.iqModulator.bband.set_state(modulator = False)
```

No command help available

**param modulator**  
OFF| ON| 1| 0

### 6.1.3.2 IqModulator

#### SCPI Command :

CALibration:IQModulator:IQModulator:[STAtE]

#### class IqModulatorCls

IqModulator commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_state()** → bool

```
# SCPI: CALibration:IQModulator:IQModulator:[STAtE]
value: bool = driver.calibration.iqModulator.iqModulator.get_state()
```

Acitvates/deactivates a separat internal adjustment procedure for the I/Q modulator.

**return**  
modulator: OFF| ON| 1| 0

**set\_state(modulator: bool)** → None

```
# SCPI: CALibration:IQModulator:IQModulator:[STAtE]
driver.calibration.iqModulator.iqModulator.set_state(modulator = False)
```

Acitvates/deactivates a separat internal adjustment procedure for the I/Q modulator.

**param modulator**  
OFF| ON| 1| 0

### 6.1.4 Level

#### SCPI Commands :

CALibration:LEVel:TEMPerature  
CALibration:LEVel:[MEASure]

#### class LevelCls

Level commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_measure()** → bool

```
# SCPI: CALibration:LEVel:[MEASure]
value: bool = driver.calibration.level.get_measure()
```

Starts all adjustments which affect the level.

**return**  
level: 1| ON| 0| OFF

**get\_temperature()** → str

```
# SCPI: CALibration:LEVel:TEMPerature
value: str = driver.calibration.level.get_temperature()
```

Queries the delta temperature since the last performed adjustment.

**return**  
temperature: string

## 6.2 Connector

**class ConnectorCls**

Connector commands group definition. 7 total commands, 2 Subgroups, 0 group commands

### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.connector.clone()
```

### Subgroups

#### 6.2.1 RefLo

**SCPI Command :**

```
CONNector:REFLo:OUTPut
```

**class RefLoCls**

RefLo commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_output()** → RefLoOutput

```
# SCPI: CONNector:REFLo:OUTPut
value: enums.RefLoOutput = driver.connector.refLo.get_output()
```

Determines the signal provided at the output connector [REF/LO OUT] (rear of the instrument) .

**return**  
output: REF| LO| OFF

**set\_output(output: RefLoOutput)** → None

```
# SCPI: CONNector:REFLo:OUTPut
driver.connector.refLo.set_output(output = enums.RefLoOutput.LO)
```

Determines the signal provided at the output connector [REF/LO OUT] (rear of the instrument) .

**param output**  
REF| LO| OFF

## 6.2.2 User<UserIx>

### RepCap Settings

```
# Range: Nr1 .. Nr48
rc = driver.connector.user.repcap_userIx_get()
driver.connector.user.repcap_userIx_set(repcap.UserIx.Nr1)
```

#### class UserCls

User commands group definition. 6 total commands, 4 Subgroups, 0 group commands Repeated Capability: UserIx, default value after init: UserIx.Nr1

### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.connector.user.clone()
```

### Subgroups

#### 6.2.2.1 Clock

##### class ClockCls

Clock commands group definition. 2 total commands, 2 Subgroups, 0 group commands

### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.connector.user.clock.clone()
```

### Subgroups

#### 6.2.2.1.1 Impedance

#### SCPI Command :

```
CONNector:USER<CH>:CLOCK:IMPedance
```

##### class ImpedanceCls

Impedance commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(userIx=UserIx.Default) → ImpG50G10K

```
# SCPI: CONNector:USER<CH>:CLOCK:IMPedance
value: enums.ImpG50G10K = driver.connector.user.clock.impedance.get(userIx =
↳repcap.UserIx.Default)
```

Selects the input impedance for the external trigger/clock inputs, when method RsSgt.Connector.User.Omode.set is set to TRIGger or CIN/COUT.

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

**return**

impedance: G50| G10K G10K Provided only for backward compatibility with other R&S signal generators. The R&S SGT accepts this values and maps it automatically to G1K.

**set**(impedance: ImpG50G10K, userIx=UserIx.Default) → None

```
# SCPI: CONNector:USER<CH>:CLOCK:IMPedance
driver.connector.user.clock.impedance.set(impedance = enums.ImpG50G10K.G10K,
↪ userIx = repcap.UserIx.Default)
```

Selects the input impedance for the external trigger/clock inputs, when method RsSgt.Connector.User.Omode.set is set to TRIGger or CIN/COUT.

**param impedance**

G50| G10K G10K Provided only for backward compatibility with other R&S signal generators. The R&S SGT accepts this values and maps it automatically to G1K.

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

### 6.2.2.1.2 Slope

#### SCPI Command :

```
CONNector:USER<CH>:CLOCK:SLOPe
```

**class SlopeCls**

Slope commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(userIx=UserIx.Default) → SlopeType

```
# SCPI: CONNector:USER<CH>:CLOCK:SLOPe
value: enums.SlopeType = driver.connector.user.clock.slope.get(userIx = repcap.
↪ UserIx.Default)
```

Sets the polarity of the active slope of an applied instrument trigger/clock.

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

**return**

slope: NEGative| POSitive

**set**(slope: SlopeType, userIx=UserIx.Default) → None

```
# SCPI: CONNector:USER<CH>:CLOCK:SLOPe
driver.connector.user.clock.slope.set(slope = enums.SlopeType.NEGative, userIx.
↪ repcap.UserIx.Default)
```

Sets the polarity of the active slope of an applied instrument trigger/clock.

**param slope**

NEGative| POSitive

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

### 6.2.2.2 Omode

#### SCPI Command :

CONNector:USER<CH>:OMODE

#### class OmodeCls

Omode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(userIx=UserIx.Default) → UserPlug

```
# SCPI: CONNector:USER<CH>:OMODE
value: enums.UserPlug = driver.connector.user.omode.get(userIx = repcap.UserIx.
↳Default)
```

Sets the operation mode of the user connector.

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

**return**

omode: MKR1| MKR2| TRIGger| CIN| COUT| SIN| SOUT| NEXT| LOW| MLATency| MARRived| HIGH| SVALid| SNValid| PVOut| PETRigger| PEMSource| TOUT MKR1/2 Marker 1/2 TRIGger Trigger TOUT Trigger out CIN Clock in COUT Clock out SIN Sync in SOUT Sync out NEXT Next trigger SVALid|SNValid Signal valid /not valid PVOut Pulse generator video out PETRigger Pulse generator external trigger PEMSource External pulse modulator source

**set**(omode: UserPlug, userIx=UserIx.Default) → None

```
# SCPI: CONNector:USER<CH>:OMODE
driver.connector.user.omode.set(omode = enums.UserPlug.CIN, userIx = repcap.
↳UserIx.Default)
```

Sets the operation mode of the user connector.

**param omode**

MKR1| MKR2| TRIGger| CIN| COUT| SIN| SOUT| NEXT| LOW| MLATency| MARRived| HIGH| SVALid| SNValid| PVOut| PETRigger| PEMSource| TOUT MKR1/2 Marker 1/2 TRIGger Trigger TOUT Trigger out CIN Clock in COUT Clock out SIN Sync in SOUT Sync out NEXT Next trigger SVALid|SNValid Signal valid /not valid PVOut Pulse generator video out PETRigger Pulse generator external trigger PEMSource External pulse modulator source

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')



### 6.2.2.3 Threshold

#### SCPI Command :

```
CONNector:USER<CH>:THReshold
```

#### class ThresholdCls

Threshold commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(*userIx=UserIx.Default*) → float

```
# SCPI: CONNector:USER<CH>:THReshold
value: float = driver.connector.user.threshold.get(userIx = repcap.UserIx.
↳Default)
```

Sets the threshold for the user connector.

#### param userIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

#### return

threshold: float Range: 0 to 2

### 6.2.2.4 Trigger

#### class TriggerCls

Trigger commands group definition. 2 total commands, 2 Subgroups, 0 group commands

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.connector.user.trigger.clone()
```

### Subgroups

#### 6.2.2.4.1 Impedance

#### SCPI Command :

```
CONNector:USER<CH>:TRIGger:IMPedance
```

#### class ImpedanceCls

Impedance commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(*userIx=UserIx.Default*) → ImpG50G10K

```
# SCPI: CONNector:USER<CH>:TRIGger:IMPedance
value: enums.ImpG50G10K = driver.connector.user.trigger.impedance.get(userIx =
↳repcap.UserIx.Default)
```

Selects the input impedance for the external trigger/clock inputs, when method RsSgt.Connector.User.Omode.set is set to TRIGger or CIN/COUT.

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

**return**

impedance: G50| G10K G10K Provided only for backward compatibility with other R&S signal generators. The R&S SGT accepts this values and maps it automatically to G1K.

**set**(impedance: ImpG50G10K, userIx=UserIx.Default) → None

```
# SCPI: CONNector:USER<CH>:TRIGger:IMPedance
driver.connector.user.trigger.impedance.set(impedance = enums.ImpG50G10K.G10K,
↪userIx = repcap.UserIx.Default)
```

Selects the input impedance for the external trigger/clock inputs, when method RsSgt.Connector.User.Omode.set is set to TRIGger or CIN/COUT.

**param impedance**

G50| G10K G10K Provided only for backward compatibility with other R&S signal generators. The R&S SGT accepts this values and maps it automatically to G1K.

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

#### 6.2.2.4.2 Slope

##### SCPI Command :

```
CONNector:USER<CH>:TRIGger:SLOPe
```

##### class SlopeCls

Slope commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(userIx=UserIx.Default) → SlopeType

```
# SCPI: CONNector:USER<CH>:TRIGger:SLOPe
value: enums.SlopeType = driver.connector.user.trigger.slope.get(userIx =
↪repcap.UserIx.Default)
```

Sets the polarity of the active slope of an applied instrument trigger/clock.

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

**return**

slope: NEGative| POSitive

**set**(slope: SlopeType, userIx=UserIx.Default) → None

```
# SCPI: CONNector:USER<CH>:TRIGger:SLOPe
driver.connector.user.trigger.slope.set(slope = enums.SlopeType.NEGative,
↳userIx = repcap.UserIx.Default)
```

Sets the polarity of the active slope of an applied instrument trigger/clock.

**param slope**

NEGative| POSitive

**param userIx**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

## 6.3 Diagnostic

### class DiagnosticCls

Diagnostic commands group definition. 1 total commands, 1 Subgroups, 0 group commands

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.clone()
```

#### Subgroups

### 6.3.1 Point

#### SCPI Command :

```
DIAGnostic:POINt:CATalog
```

### class PointCls

Point commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_catalog()** → List[str]

```
# SCPI: DIAGnostic:POINt:CATalog
value: List[str] = driver.diagnostic.point.get_catalog()
```

Queries the test points available in the instrument.

**return**

diag\_poin\_id\_cat: No help available

## 6.4 MassMemory

### SCPI Commands :

```
MMEMory:CDIRectory
MMEMory:COPY
MMEMory:DELeTe
MMEMory:DRIVes
MMEMory:MDIRectory
MMEMory:MOVE
MMEMory:MSIS
MMEMory:RDIRectory
MMEMory:RDIRectory:REcursive
```

#### class MassMemoryCls

MassMemory commands group definition. 15 total commands, 4 Subgroups, 9 group commands

**copy**(source\_file: str, destination\_file: str) → None

```
# SCPI: MMEMory:COPY
driver.massMemory.copy(source_file = 'abc', destination_file = 'abc')
```

Copies an existing file to a new file. Instead of just a file, this command can also be used to copy a complete directory together with all its files.

**param source\_file**

string String containing the path and file name of the source file

**param destination\_file**

string String containing the path and name of the target file. The path can be relative or absolute. If DestinationFile is not specified, the SourceFile is copied to the current directory, queried with the method RsSgt.MassMemory.currentDirectory command.  
Note: Existing files with the same name in the destination directory are overwritten without an error message.

**delete**(filename: str) → None

```
# SCPI: MMEMory:DELeTe
driver.massMemory.delete(filename = 'abc')
```

Removes a file from the specified directory.

**param filename**

string String parameter to specify the name and directory of the file to be removed.

**delete\_directory**(directory: str) → None

```
# SCPI: MMEMory:RDIRectory
driver.massMemory.delete_directory(directory = 'abc')
```

Removes an existing directory from the mass memory storage system. If no directory is specified, the subdirectory with the specified name is deleted in the default directory.

**param directory**

string String parameter to specify the directory to be deleted.

**delete\_directory\_recursive**(*directory: str*) → None

```
# SCPI: MMEemory:RDIReactory:REcursive
driver.massMemory.delete_directory_recursive(directory = 'abc')
```

No command help available

**param directory**  
No help available

**get\_current\_directory**() → str

```
# SCPI: MMEemory:CDIReactory
value: str = driver.massMemory.get_current_directory()
```

Changes the default directory for mass memory storage. The directory is used for all subsequent MMEM commands if no path is specified with them.

**return**  
directory: directory\_name String containing the path to another directory. The path can be relative or absolute. To change to a higher directory, use two dots '..'.

**get\_drives**() → str

```
# SCPI: MMEemory:DRIVes
value: str = driver.massMemory.get_drives()
```

No command help available

**return**  
drive\_list: No help available

**get\_msis**() → str

```
# SCPI: MMEemory:MSIS
value: str = driver.massMemory.get_msis()
```

Defines the drive or network resource (in the case of networks) for instruments with windows operating system, using msis (MSIS = Mass Storage Identification String) . Note: Instruments with Linux operating system ignore this command, since Linux does not use drive letter assignment.

**return**  
path: No help available

**make\_directory**(*directory: str*) → None

```
# SCPI: MMEemory:MDIReactory
driver.massMemory.make_directory(directory = 'abc')
```

Creates a subdirectory for mass memory storage in the specified directory. If no directory is specified, a subdirectory is created in the default directory. This command can also be used to create a directory tree.

**param directory**  
string String parameter to specify the new directory.

**move**(*source\_file: str, destination\_file: str*) → None

```
# SCPI: MMEemory:MOVE
driver.massMemory.move(source_file = 'abc', destination_file = 'abc')
```

Moves an existing file to a new location or, if no path is specified, renames an existing file.

**param source\_file**

string String parameter to specify the name of the file to be moved.

**param destination\_file**

string String parameters to specify the name of the new file.

**set\_current\_directory**(*directory: str*) → None

```
# SCPI: MMEemory:CDIRectory
driver.massMemory.set_current_directory(directory = 'abc')
```

Changes the default directory for mass memory storage. The directory is used for all subsequent MMEM commands if no path is specified with them.

**param directory**

directory\_name String containing the path to another directory. The path can be relative or absolute. To change to a higher directory, use two dots '..' .

**set\_msis**(*path: str*) → None

```
# SCPI: MMEemory:MSIS
driver.massMemory.set_msis(path = 'abc')
```

Defines the drive or network resource (in the case of networks) for instruments with windows operating system, using msis (MSIS = Mass Storage Identification String) . Note: Instruments with Linux operating system ignore this command, since Linux does not use drive letter assignment.

**param path**

No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.clone()
```

## Subgroups

### 6.4.1 Catalog

#### SCPI Command :

```
MMEMory:CATalog
```

#### class CatalogCls

Catalog commands group definition. 2 total commands, 1 Subgroups, 1 group commands

**get\_value**() → str

```
# SCPI: MMEemory:CATalog
value: str = driver.massMemory.catalog.get_value()
```

Returns the content of a particular directory.

**return**  
catalog: No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.catalog.clone()
```

## Subgroups

### 6.4.1.1 Length

#### SCPI Command :

```
MMEMory:CATalog:LENGth
```

#### class LengthCls

Length commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(path: str = None) → int

```
# SCPI: MMEMory:CATalog:LENGth
value: int = driver.massMemory.catalog.length.get(path = 'abc')
```

Returns the number of files in the current or in the specified directory.

#### param path

string String parameter to specify the directory. If the directory is omitted, the command queries the content of the current directory, queried with method RsSgt.MassMemory.currentDirectory command.

#### return

file\_count: integer Number of files.

### 6.4.2 Dcatalog

#### SCPI Command :

```
MMEMory:DCATalog
```

#### class DcatalogCls

Dcatalog commands group definition. 2 total commands, 1 Subgroups, 1 group commands

**get\_value**() → str

```
# SCPI: MMEMory:DCATalog
value: str = driver.massMemory.dcatalog.get_value()
```

Returns the subdirectories of a particular directory.

#### return

dcatalog: No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.dcatalog.clone()
```

## Subgroups

### 6.4.2.1 Length

#### SCPI Command :

```
MMEMory:DCATalog:LENGth
```

#### class LengthCls

Length commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(path: str = None) → int

```
# SCPI: MMEMory:DCATalog:LENGth
value: int = driver.massMemory.dcatalog.length.get(path = 'abc')
```

Returns the number of subdirectories in the current or specified directory.

**param path**

String parameter to specify the directory. If the directory is omitted, the command queries the contents of the current directory, to be queried with method RsSgt.MassMemory.currentDirectory command.

**return**

directory\_count: integer Number of parent and subdirectories.

### 6.4.3 Load

#### class LoadCls

Load commands group definition. 1 total commands, 1 Subgroups, 0 group commands

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.load.clone()
```



## Subgroups

### 6.4.3.1 State

#### SCPI Command :

```
MMEMory:LOAD:STATe
```

#### class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**set**(data\_set: int, source\_file: str) → None

```
# SCPI: MMEMory:LOAD:STATe
driver.massMemory.load.state.set(data_set = 1, source_file = 'abc')
```

Loads the specified file stored under the specified name in an internal memory. After the file has been loaded, the instrument setting must be activated using an \*RCL command.

**param data\_set**  
No help available

**param source\_file**  
No help available

## 6.4.4 Store

#### class StoreCls

Store commands group definition. 1 total commands, 1 Subgroups, 0 group commands

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.store.clone()
```

## Subgroups

### 6.4.4.1 State

#### SCPI Command :

```
MMEMory:STORe:STATe
```

#### class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**set**(data\_set: int, destination\_file: str) → None

```
# SCPI: MMEMory:STORe:STATe
driver.massMemory.store.state.set(data_set = 1, destination_file = 'abc')
```

Stores the current instrument setting in the specified file. The instrument setting must first be stored in an internal memory with the same number using the common command *\*SAV*.

**param data\_set**

No help available

**param destination\_file**

No help available

## 6.5 Output

### SCPI Command :

```
OUTPut<HW>:AMODE
```

#### class OutputCls

Output commands group definition. 6 total commands, 3 Subgroups, 1 group commands

**get\_amode()** → AttMode

```
# SCPI: OUTPut<HW>:AMODE
value: enums.AttMode = driver.output.get_amode()
```

Switches the mode of the attenuator at the RF output.

**return**

amode: AUTO| FIXEd| APASSive AUTO The attenuator is switched automatically. The level settings are made in the full range. APASSive The attenuator is switched automatically. The level settings are made only for the passive reference circuits. The high-level ranges are not available. FIXEd The level settings are made without switching the attenuator. When this operating mode is switched on, the attenuator is fixed to its current position and the resulting variation range is defined.

**set\_amode(amode: AttMode)** → None

```
# SCPI: OUTPut<HW>:AMODE
driver.output.set_amode(amode = enums.AttMode.APASSive)
```

Switches the mode of the attenuator at the RF output.

**param amode**

AUTO| FIXEd| APASSive AUTO The attenuator is switched automatically. The level settings are made in the full range. APASSive The attenuator is switched automatically. The level settings are made only for the passive reference circuits. The high-level ranges are not available. FIXEd The level settings are made without switching the attenuator. When this operating mode is switched on, the attenuator is fixed to its current position and the resulting variation range is defined.

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.output.clone()
```

## Subgroups

### 6.5.1 Afixed

#### class AfixedCls

Afixed commands group definition. 2 total commands, 1 Subgroups, 0 group commands

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.output.afixed.clone()
```

## Subgroups

### 6.5.1.1 Range

#### SCPI Commands :

```
OUTPut<HW>:AFIXed:RANGe:LOWer
OUTPut<HW>:AFIXed:RANGe:UPPer
```

#### class RangeCls

Range commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_lower()** → float

```
# SCPI: OUTPut<HW>:AFIXed:RANGe:LOWer
value: float = driver.output.afixed.range.get_lower()
```

Queries the minimum level which can be set without the attenuator being adjusted (Attenuator FIXED) .

```
return
lower: float
```

**get\_upper()** → float

```
# SCPI: OUTPut<HW>:AFIXed:RANGe:UPPer
value: float = driver.output.afixed.range.get_upper()
```

Queries the maximum level which can be set without the attenuator being adjusted (Attenuator FIXED) .

```
return
upper: float
```

## 6.5.2 Protection

### SCPI Command :

```
OUTPut<HW>:PROTectiOn:CLEar
```

#### class ProtectionCls

Protection commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**clear()** → None

```
# SCPI: OUTPut<HW>:PROTectiOn:CLEar
driver.output.protection.clear()
```

No command help available

**clear\_with\_opc**(opc\_timeout\_ms: int = -1) → None

```
# SCPI: OUTPut<HW>:PROTectiOn:CLEar
driver.output.protection.clear_with_opc()
```

No command help available

Same as clear, but waits for the operation to complete before continuing further. Use the RsSgt.utilities.opc\_timeout\_set() to set the timeout value.

**param opc\_timeout\_ms**

Maximum time to wait in milliseconds, valid only for this call.

## 6.5.3 State

### SCPI Commands :

```
OUTPut<HW>:[STATe]:PON
OUTPut<HW>:[STATe]
```

#### class StateCls

State commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_pon()** → PowOutpPonMode

```
# SCPI: OUTPut<HW>:[STATe]:PON
value: enums.PowOutpPonMode = driver.output.state.get_pon()
```

Selects the state of the RF output when the instrument is switched on.

**return**

pon: OFF| UNCHanged OFF Deactivates the output when the instrument is switched on ([RF off]) . UNCHanged Restores the initial state of the RF output before the last turn off.

**get\_value()** → bool

```
# SCPI: OUTPut<HW>:[STATe]
value: bool = driver.output.state.get_value()
```

Activates the RF output signal ([RF on/off]) .

**return**  
state: 1| ON| 0| OFF

**set\_pon**(pon: *PowOutpPonMode*) → None

```
# SCPI: OUTPut<HW>:[STATe]:PON
driver.output.state.set_pon(pon = enums.PowOutpPonMode.OFF)
```

Selects the state of the RF output when the instrument is switched on.

**param pon**  
OFF| UNCHanged OFF Deactivates the output when the instrument is switched on ([RF off]) . UNCHanged Restores the initial state of the RF output before the last turn off.

**set\_value**(state: *bool*) → None

```
# SCPI: OUTPut<HW>:[STATe]
driver.output.state.set_value(state = False)
```

Activates the RF output signal ([RF on/off]) .

**param state**  
1| ON| 0| OFF

## 6.6 Sconfiguration

**SCPI Command :**

SCONfiguration:MODE

**class SconfigurationCls**

Sconfiguration commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_mode**() → *BbSystemConfiguration*

```
# SCPI: SCONfiguration:MODE
value: enums.BbSystemConfiguration = driver.sconfiguration.get_mode()
```

Switches between standard mode and ARB mode for envelope tracking.

**return**  
configuration: STANdard| AFETracking STANdard Standard mode used for signal generation. AFETracking ARB foe Envelope Tracking: enables the usage of an extra baseband for enabling the envelope tracking ARB generation.

**set\_mode**(configuration: *BbSystemConfiguration*) → None

```
# SCPI: SCONfiguration:MODE
driver.sconfiguration.set_mode(configuration = enums.BbSystemConfiguration.
    AFETracking)
```

Switches between standard mode and ARB mode for envelope tracking.

**param configuration**

STANdard| AFETracking STANdard Standard mode used for signal generation. AFE-Tracking ARB foe Envelope Tracking: enables the usage of an extra baseband for enabling the envelope tracking ARB generation.

## 6.7 Source

**SCPI Command :**

```
[SOURce<HW>]:OPMode
```

**class SourceCls**

Source commands group definition. 64 total commands, 9 Subgroups, 1 group commands

**get\_op\_mode()** → OpMode

```
# SCPI: [SOURce<HW>]:OPMode
value: enums.OpMode = driver.source.get_op_mode()
```

Sets the operation mode.

**return**

op\_mode: NORMal| BBBYpass NORMal normal operation BBBYpass Baseband by-pass mode

**set\_op\_mode(op\_mode: OpMode)** → None

```
# SCPI: [SOURce<HW>]:OPMode
driver.source.set_op_mode(op_mode = enums.OpMode.BBBYpass)
```

Sets the operation mode.

**param op\_mode**

NORMal| BBBYpass NORMal normal operation BBBYpass Baseband bypass mode

**Cloning the Group**

```
# Create a clone of the original group, that exists independently
group2 = driver.source.clone()
```

**Subgroups**

### 6.7.1 Bb

**SCPI Commands :**

```
[SOURce<HW>]:BB:FOFFset
[SOURce<HW>]:BB:POFFset
```

**class BbCls**

Bb commands group definition. 8 total commands, 1 Subgroups, 2 group commands

**get\_foffset()** → float

```
# SCPI: [SOURCE<HW>]:BB:FOFFset
value: float = driver.source.bb.get_foffset()
```

Sets the frequency offset for the baseband signal. The offset affects the signal on the baseband block output. It shifts the useful baseband signal in the center frequency.

**return**  
foffset: float

**get\_poffset()** → float

```
# SCPI: [SOURCE<HW>]:BB:POFFset
value: float = driver.source.bb.get_poffset()
```

Sets the relative phase offset of the baseband signal. The phase offset affects the signal of the 'Baseband Block' output.

**return**  
ph\_offset: float

**set\_foffset(foffset: float)** → None

```
# SCPI: [SOURCE<HW>]:BB:FOFFset
driver.source.bb.set_foffset(foffset = 1.0)
```

Sets the frequency offset for the baseband signal. The offset affects the signal on the baseband block output. It shifts the useful baseband signal in the center frequency.

**param foffset**  
float

**set\_poffset(ph\_offset: float)** → None

```
# SCPI: [SOURCE<HW>]:BB:POFFset
driver.source.bb.set_poffset(ph_offset = 1.0)
```

Sets the relative phase offset of the baseband signal. The phase offset affects the signal of the 'Baseband Block' output.

**param ph\_offset**  
float

**Cloning the Group**

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.clone()
```

## Subgroups

### 6.7.1.1 Impairment

#### class ImpairmentCls

Impairment commands group definition. 6 total commands, 2 Subgroups, 0 group commands

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.impairment.clone()
```

## Subgroups

### 6.7.1.1.1 Bbmm<IqConnector>

#### RepCap Settings

```
# Range: Nr1 .. Nr4
rc = driver.source.bb.impairment.bbmm.repcap_iqConnector_get()
driver.source.bb.impairment.bbmm.repcap_iqConnector_set(repcap.IqConnector.Nr1)
```

#### class BbmmCls

Bbmm commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: IqConnector, default value after init: IqConnector.Nr1

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.impairment.bbmm.clone()
```

## Subgroups

### 6.7.1.1.1.1 Poffset

#### SCPI Command :

```
[SOURce]:BB:IMPairment:BBMM<CH>:POFFset
```

#### class PoffsetCls

Poffset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(iqConnector=IqConnector.Default) → float

```
# SCPI: [SOURce]:BB:IMPairment:BBMM<CH>:POFFset
value: float = driver.source.bb.impairment.bbmm.poffset.get(iqConnector = ↵
↵repcap.IqConnector.Default)
```



No command help available

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Bbmm')

**return**

phase\_offset: No help available

**set**(phase\_offset: float, iqConnector=*IqConnector.Default*) → None

```
# SCPI: [SOURce]:BB:IMPAirment:BBMM<CH>:POFFset
driver.source.bb.impairment.bbmm.poffset.set(phase_offset = 1.0, iqConnector =
↳ repcap.IqConnector.Default)
```

No command help available

**param phase\_offset**

No help available

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Bbmm')

#### 6.7.1.1.2 IqOutput<IqConnector>

##### RepCap Settings

```
# Range: Nr1 .. Nr4
rc = driver.source.bb.impairment.iqOutput.repcap_iqConnector_get()
driver.source.bb.impairment.iqOutput.repcap_iqConnector_set(repcap.IqConnector.Nr1)
```

**class IqOutputCls**

IqOutput commands group definition. 5 total commands, 4 Subgroups, 0 group commands Repeated Capability: IqConnector, default value after init: IqConnector.Nr1

##### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.impairment.iqOutput.clone()
```

##### Subgroups

#### 6.7.1.1.2.1 IqRatio

**class IqRatioCls**

IqRatio commands group definition. 1 total commands, 1 Subgroups, 0 group commands

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.impairment.iqOutput.iqRatio.clone()
```

## Subgroups

### 6.7.1.1.2.2 Magnitude

#### SCPI Command :

```
[SOURce]:BB:IMPairment:IQOutput<CH>:IQRatio:[MAGNitude]
```

#### class MagnitudeCls

Magnitude commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(iqConnector=IqConnector.Default) → float

```
# SCPI: [SOURce]:BB:IMPairment:IQOutput<CH>:IQRatio:[MAGNitude]
value: float = driver.source.bb.impairment.iqOutput.iqRatio.magnitude.
↪get(iqConnector = repcap.IqConnector.Default)
```

Sets the ratio of I modulation to Q modulation (amplification imbalance) of the corresponding digital I/Q channel. The input may be either in dB or %. The resolution is 0.001 dB, an input in percent is rounded to the closest valid value in dB. A query returns the value in dB.

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

#### param iqConnector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

#### return

ipartq\_ratio: No help available

**set**(ipartq\_ratio: float, iqConnector=IqConnector.Default) → None

```
# SCPI: [SOURce]:BB:IMPairment:IQOutput<CH>:IQRatio:[MAGNitude]
driver.source.bb.impairment.iqOutput.iqRatio.magnitude.set(ipartq_ratio = 1.0, ↪
↪iqConnector = repcap.IqConnector.Default)
```

Sets the ratio of I modulation to Q modulation (amplification imbalance) of the corresponding digital I/Q channel. The input may be either in dB or %. The resolution is 0.001 dB, an input in percent is rounded to the closest valid value in dB. A query returns the value in dB.

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param ipartq\_ratio**

float Range: -1 to 1

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

### 6.7.1.1.2.3 Leakage

**class LeakageCls**

Leakage commands group definition. 2 total commands, 2 Subgroups, 0 group commands

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.impairment.iqOutput.leakage.clone()
```

### Subgroups

### 6.7.1.1.2.4 Icomponent

#### SCPI Command :

```
[SOURce]:BB:IMPairment:IQOutput<CH>:LEAKage:I
```

**class IcomponentCls**

Icomponent commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(iqConnector=*IqConnector.Default*) → float

```
# SCPI: [SOURce]:BB:IMPairment:IQOutput<CH>:LEAKage:I
value: float = driver.source.bb.impairment.iqOutput.leakage.icomponent.
↪get(iqConnector = repcap.IqConnector.Default)
```

**Determines the leakage amplitude of the I or Q-signal component of the corresponding stream.**

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

**return**

ipart: No help available

**set**(ipart: float, iqConnector=*IqConnector.Default*) → None

```
# SCPI: [SOURCE]:BB:IMPAirment:IQOutput<CH>:LEAKage:I
driver.source.bb.impairment.iqOutput.leakage.icomponent.set(ipart = 1.0,
↪ iqConnector = repcap.IqConnector.Default)
```

**Determines the leakage amplitude of the I or Q-signal component of the corresponding stream.**

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param ipart**

float Range: -10 to 10

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

### 6.7.1.1.2.5 Qcomponent

#### SCPI Command :

```
[SOURCE]:BB:IMPAirment:IQOutput<CH>:LEAKage:Q
```

#### class QcomponentCls

Qcomponent commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(iqConnector=*IqConnector.Default*) → float

```
# SCPI: [SOURCE]:BB:IMPAirment:IQOutput<CH>:LEAKage:Q
value: float = driver.source.bb.impairment.iqOutput.leakage.qcomponent.
↪ get(iqConnector = repcap.IqConnector.Default)
```

**Determines the leakage amplitude of the I or Q-signal component of the corresponding stream.**

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

**return**

qpart: No help available

**set**(qpart: float, iqConnector=*IqConnector.Default*) → None

```
# SCPI: [SOURCE]:BB:IMPAirment:IQOutput<CH>:LEAKage:Q
driver.source.bb.impairment.iqOutput.leakage.qcomponent.set(qpart = 1.0,
↪ iqConnector = repcap.IqConnector.Default)
```

**Determines the leakage amplitude of the I or Q-signal component of the corresponding stream.**

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param qpart**

float Range: -10 to 10

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

#### 6.7.1.1.2.6 Quadrature

##### class QuadratureCls

Quadrature commands group definition. 1 total commands, 1 Subgroups, 0 group commands

##### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.impairment.iqOutput.quadrature.clone()
```

##### Subgroups

#### 6.7.1.1.2.7 Angle

##### SCPI Command :

```
[SOURce]:BB:IMPairment:IQOutput<CH>:QUADrature:[ANGLE]
```

##### class AngleCls

Angle commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(iqConnector=*IqConnector.Default*) → float

```
# SCPI: [SOURce]:BB:IMPairment:IQOutput<CH>:QUADrature:[ANGLE]
value: float = driver.source.bb.impairment.iqOutput.quadrature.angle.
↪get(iqConnector = repcap.IqConnector.Default)
```

**Sets the quadrature offset. A positive quadrature offset results in a phase angle greater than 90 degrees.**

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

**return**  
angle: float Range: -10 to 10  
**set**(angle: float, iqConnector=IqConnector.Default) → None

```
# SCPI: [SOURCE]:BB:IMPairment:IQOutput<CH>:QUADrature:[ANGLE]
driver.source.bb.impairment.iqOutput.quadrature.angle.set(angle = 1.0,
↪iqConnector = repcap.IqConnector.Default)
```

**Sets the quadrature offset. A positive quadrature offset results in a phase angle greater than 90 degrees.**

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param angle**  
float Range: -10 to 10

**param iqConnector**  
optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

#### 6.7.1.1.2.8 State

##### SCPI Command :

```
[SOURCE]:BB:IMPairment:IQOutput<CH>:STATe
```

##### class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(iqConnector=IqConnector.Default) → bool

```
# SCPI: [SOURCE]:BB:IMPairment:IQOutput<CH>:STATe
value: bool = driver.source.bb.impairment.iqOutput.state.get(iqConnector =
↪repcap.IqConnector.Default)
```

**Activates the impairment or correction values LEAKage, QUADrature and IQRatio for the corresponding stream.**

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param iqConnector**  
optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

**return**  
state: 0| 1| OFF| ON

**set**(state: bool, iqConnector=IqConnector.Default) → None

```
# SCPI: [SOURCE]:BB:IMPAirment:IQOutput<CH>:STATE
driver.source.bb.impairment.iqOutput.state.set(state = False, iqConnector =
↳repcap.IqConnector.Default)
```

**Activates the impairment or correction values LEAKage, QUADrature and IQRatio for the corresponding stream.**

INTRO\_CMD\_HELP: The suffix <ch> has the following values:

- <ch>= 0: I/Q Analog Outputs
- <ch>= 1: I/Q Modulator Digital Impairments

**param state**

0| 1| OFF| ON

**param iqConnector**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'IqOutput')

## 6.7.2 Bbin

**SCPI Command :**

```
[SOURCE<HW>]:BBIN:ODELAY
```

**class BbinCls**

Bbin commands group definition. 2 total commands, 1 Subgroups, 1 group commands

**get\_odelay**() → float

```
# SCPI: [SOURCE<HW>]:BBIN:ODELAY
value: float = driver.source.bbin.get_odelay()
```

Seds the output delay of the external baseband signal.

**return**

delay: float Range: 0 to 1

**set\_odelay**(delay: float) → None

```
# SCPI: [SOURCE<HW>]:BBIN:ODELAY
driver.source.bbin.set_odelay(delay = 1.0)
```

Seds the output delay of the external baseband signal.

**param delay**

float Range: 0 to 1

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bbin.clone()
```

## Subgroups

### 6.7.2.1 SymbolRate

#### SCPI Command :

```
[SOURce<HW>]:BBIN:SRATe:[ACTual]
```

#### class SymbolRateCls

SymbolRate commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_actual()** → float

```
# SCPI: [SOURce<HW>]:BBIN:SRATe:[ACTual]
value: float = driver.source.bbin.symbolRate.get_actual()
```

Sets the sample rate of the external digital baseband signal.

**return**

actual: float Range: 25E6 to 250E6

**set\_actual(actual: float)** → None

```
# SCPI: [SOURce<HW>]:BBIN:SRATe:[ACTual]
driver.source.bbin.symbolRate.set_actual(actual = 1.0)
```

Sets the sample rate of the external digital baseband signal.

**param actual**

float Range: 25E6 to 250E6

### 6.7.3 Frequency

#### SCPI Command :

```
[SOURce]:FREQuency:OFFSet
```

#### class FrequencyCls

Frequency commands group definition. 9 total commands, 2 Subgroups, 1 group commands

**get\_offset()** → float

```
# SCPI: [SOURce]:FREQuency:OFFSet
value: float = driver.source.frequency.get_offset()
```

Sets a frequency offset, for example include the frequency shift of downstream instrument. Note: Enabled frequency offset affects the result of the query SOURce:FREQuency:CW? The query returns the frequency, including frequency offset.



**return**  
offset: float Range: -3e9 to 3e9

**set\_offset**(offset: float) → None

```
# SCPI: [SOURCE]:FREQUENCY:OFFSET
driver.source.frequency.set_offset(offset = 1.0)
```

Sets a frequency offset, for example include the frequency shift of downstream instrument. Note: Enabled frequency offset affects the result of the query SOURce:FREQUENCY:CW? The query returns the frequency, including frequency offset.

**param offset**  
float Range: -3e9 to 3e9

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.frequency.clone()
```

## Subgroups

### 6.7.3.1 Cw

#### SCPI Commands :

```
[SOURCE<HW>]:FREQUENCY:[CW]:RCL
[SOURCE<HW>]:FREQUENCY:[CW]
```

#### class CwCls

Cw commands group definition. 4 total commands, 1 Subgroups, 2 group commands

**get\_recall**() → InclExcl

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]:RCL
value: enums.InclExcl = driver.source.frequency.cw.get_recall()
```

No command help available

**return**  
rcl\_excl\_freq: No help available

**get\_value**() → float

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]
value: float = driver.source.frequency.cw.get_value()
```

Sets the RF frequency at the RF output connector of the selected instrument. Note: Enabled frequency offset affects the result of this query. The query returns the frequency, including frequency offset.

**return**  
cw: float

**set\_recall**(*rcl\_excl\_freq*: *InclExcl*) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]:RCL
driver.source.frequency.cw.set_recall(rcl_excl_freq = enums.InclExcl.EXCLUDE)
```

No command help available

**param rcl\_excl\_freq**

No help available

**set\_value**(*cw*: *float*) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]
driver.source.frequency.cw.set_value(cw = 1.0)
```

Sets the RF frequency at the RF output connector of the selected instrument. Note: Enabled frequency offset affects the result of this query. The query returns the frequency, including frequency offset.

**param cw**

float

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.frequency.cw.clone()
```

## Subgroups

### 6.7.3.1.1 Step

#### SCPI Commands :

```
[SOURCE<HW>]:FREQUENCY:[CW]:STEP:MODE
[SOURCE<HW>]:FREQUENCY:[CW]:STEP:[INCRement]
```

#### class StepCls

Step commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_increment**() → float

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]:STEP:[INCRement]
value: float = driver.source.frequency.cw.step.get_increment()
```

No command help available

**return**

freq\_step: No help available

**get\_mode**() → FreqStepMode

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]:STEP:MODE
value: enums.FreqStepMode = driver.source.frequency.cw.step.get_mode()
```

No command help available

**return**

freq\_step\_mode: No help available

**set\_increment**(freq\_step: float) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]:STEP:[INCREMENT]
driver.source.frequency.cw.step.set_increment(freq_step = 1.0)
```

No command help available

**param freq\_step**

No help available

**set\_mode**(freq\_step\_mode: FreqStepMode) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]:STEP:MODE
driver.source.frequency.cw.step.set_mode(freq_step_mode = enums.FreqStepMode.
    DECIMAL)
```

No command help available

**param freq\_step\_mode**

No help available

### 6.7.3.2 Fixed

#### SCPI Commands :

```
[SOURCE<HW>]:FREQUENCY:[FIXED]:RCL
[SOURCE<HW>]:FREQUENCY:[FIXED]
```

#### class FixedCls

Fixed commands group definition. 4 total commands, 1 Subgroups, 2 group commands

**get\_recall**() → InclExcl

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[FIXED]:RCL
value: enums.InclExcl = driver.source.frequency.fixed.get_recall()
```

No command help available

**return**

rcl\_excl\_freq: No help available

**get\_value**() → float

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[FIXED]
value: float = driver.source.frequency.fixed.get_value()
```

Sets the RF frequency at the RF output connector of the selected instrument. Note: Enabled frequency offset affects the result of this query. The query returns the frequency, including frequency offset.

**return**

cw: float

**set\_recall**(*rcl\_excl\_freq*: *InclExcl*) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[FIXed]:RCL
driver.source.frequency.fixed.set_recall(rcl_excl_freq = enums.InclExcl.EXCLUDE)
```

No command help available

**param rcl\_excl\_freq**

No help available

**set\_value**(*cw*: *float*) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[FIXed]
driver.source.frequency.fixed.set_value(cw = 1.0)
```

Sets the RF frequency at the RF output connector of the selected instrument. Note: Enabled frequency offset affects the result of this query. The query returns the frequency, including frequency offset.

**param cw**

float

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.frequency.fixed.clone()
```

## Subgroups

### 6.7.3.2.1 Step

#### SCPI Commands :

```
[SOURCE<HW>]:FREQUENCY:[FIXed]:STEP:MODE
[SOURCE<HW>]:FREQUENCY:[FIXed]:STEP:[INCRement]
```

#### class StepCls

Step commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_increment**() → float

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[FIXed]:STEP:[INCRement]
value: float = driver.source.frequency.fixed.step.get_increment()
```

No command help available

**return**

freq\_step: No help available

**get\_mode**() → FreqStepMode

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[FIXed]:STEP:MODE
value: enums.FreqStepMode = driver.source.frequency.fixed.step.get_mode()
```

No command help available

**return**

freq\_step\_mode: No help available

**set\_increment**(freq\_step: float) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[FIXed]:STEP:[INCRement]
driver.source.frequency.fixed.step.set_increment(freq_step = 1.0)
```

No command help available

**param freq\_step**

No help available

**set\_mode**(freq\_step\_mode: FreqStepMode) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[FIXed]:STEP:MODE
driver.source.frequency.fixed.step.set_mode(freq_step_mode = enums.FreqStepMode.
↳DECimal)
```

No command help available

**param freq\_step\_mode**

No help available

## 6.7.4 InputPy

**class InputPyCls**

InputPy commands group definition. 4 total commands, 2 Subgroups, 0 group commands

### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.inputPy.clone()
```

## Subgroups

### 6.7.4.1 Modext

**SCPI Command :**

```
[SOURCE]:INPut:MODext:IMPedance
```

**class ModextCls**

Modext commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_impedance**() → ImpG50G10K

```
# SCPI: [SOURCE]:INPut:MODext:IMPedance
value: enums.ImpG50G10K = driver.source.inputPy.modext.get_impedance()
```

No command help available

**return**  
impedance: No help available

**set\_impedance**(*impedance: ImpG50G10K*) → None

```
# SCPI: [SOURCE]:INPut:MODext:IMPedance
driver.source.inputPy.modext.set_impedance(impedance = enums.ImpG50G10K.G10K)
```

No command help available

**param impedance**  
No help available

### 6.7.4.2 Trigger

#### SCPI Commands :

```
[SOURCE<HW>]:INPut:TRIGger:IMPedance
[SOURCE<HW>]:INPut:TRIGger:LEVel
```

#### class TriggerCls

Trigger commands group definition. 3 total commands, 1 Subgroups, 2 group commands

**get\_impedance**() → InputImpRf

```
# SCPI: [SOURCE<HW>]:INPut:TRIGger:IMPedance
value: enums.InputImpRf = driver.source.inputPy.trigger.get_impedance()
```

No command help available

**return**  
impedance: No help available

**get\_level**() → float

```
# SCPI: [SOURCE<HW>]:INPut:TRIGger:LEVel
value: float = driver.source.inputPy.trigger.get_level()
```

No command help available

**return**  
level: No help available

**set\_impedance**(*impedance: InputImpRf*) → None

```
# SCPI: [SOURCE<HW>]:INPut:TRIGger:IMPedance
driver.source.inputPy.trigger.set_impedance(impedance = enums.InputImpRf.G10K)
```

No command help available

**param impedance**  
No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.inputPy.trigger.clone()
```

## Subgroups

### 6.7.4.2.1 Bband

#### SCPI Command :

```
[SOURce<HW>]:INPut:TRIGger:[BBANd]:SLOPe
```

#### class BbandCls

Bband commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_slope()** → SlopeType

```
# SCPI: [SOURce<HW>]:INPut:TRIGger:[BBANd]:SLOPe
value: enums.SlopeType = driver.source.inputPy.trigger.bband.get_slope()
```

No command help available

**return**  
slope: No help available

**set\_slope(slope: SlopeType)** → None

```
# SCPI: [SOURce<HW>]:INPut:TRIGger:[BBANd]:SLOPe
driver.source.inputPy.trigger.bband.set_slope(slope = enums.SlopeType.NEGative)
```

No command help available

**param slope**  
No help available

## 6.7.5 Iq

#### SCPI Commands :

```
[SOURce<HW>]:IQ:CREStfactor
[SOURce<HW>]:IQ:SOURce
[SOURce<HW>]:IQ:STATe
[SOURce<HW>]:IQ:WBState
```

#### class IqCls

Iq commands group definition. 10 total commands, 1 Subgroups, 4 group commands

**get\_crest\_factor()** → float

```
# SCPI: [SOURce<HW>]:IQ:CREStfactor
value: float = driver.source.iq.get_crest_factor()
```

Sets the crest factor of the IQ modulation signal.

**return**  
crest\_factor: float Range: 0 to 80

**get\_source()** → IqMode

```
# SCPI: [SOURCE<HW>]:IQ:SOURCE
value: enums.IqMode = driver.source.iq.get_source()
```

Sets the input signal for the I/Q modulator.

**return**  
source: ANALog| BAsEband

**get\_state()** → bool

```
# SCPI: [SOURCE<HW>]:IQ:STATE
value: bool = driver.source.iq.get_state()
```

Switches the I/Q modulation on and off.

**return**  
state: 1| ON| 0| OFF

**get\_wb\_state()** → bool

```
# SCPI: [SOURCE<HW>]:IQ:WBSTATE
value: bool = driver.source.iq.get_wb_state()
```

Selects optimized settings for wideband modulation signals.

**return**  
state: 1| ON| 0| OFF

**set\_crest\_factor**(crest\_factor: float) → None

```
# SCPI: [SOURCE<HW>]:IQ:CRESTfactor
driver.source.iq.set_crest_factor(crest_factor = 1.0)
```

Sets the crest factor of the IQ modulation signal.

**param crest\_factor**  
float Range: 0 to 80

**set\_source**(source: IqMode) → None

```
# SCPI: [SOURCE<HW>]:IQ:SOURCE
driver.source.iq.set_source(source = enums.IqMode.ANALog)
```

Sets the input signal for the I/Q modulator.

**param source**  
ANALog| BAsEband

**set\_state**(state: bool) → None

```
# SCPI: [SOURCE<HW>]:IQ:STATE
driver.source.iq.set_state(state = False)
```



Switches the I/Q modulation on and off.

**param state**  
1| ON| 0| OFF

**set\_wb\_state**(state: bool) → None

```
# SCPI: [SOURCE<HW>]:IQ:WBState
driver.source.iq.set_wb_state(state = False)
```

Selects optimized settings for wideband modulation signals.

**param state**  
1| ON| 0| OFF

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.iq.clone()
```

## Subgroups

### 6.7.5.1 Impairment

#### SCPI Command :

```
[SOURCE<HW>]:IQ:IMPAirment:[STATe]
```

#### class ImpairmentCls

Impairment commands group definition. 6 total commands, 4 Subgroups, 1 group commands

**get\_state**() → bool

```
# SCPI: [SOURCE<HW>]:IQ:IMPAirment:[STATe]
value: bool = driver.source.iq.impairment.get_state()
```

Activates/ deactivates the three impairment or correction values LEAKage, QUADrature and IQRatio for the baseband signal prior to input into the I/Q modulator.

**return**  
state: 1| ON| 0| OFF

**set\_state**(state: bool) → None

```
# SCPI: [SOURCE<HW>]:IQ:IMPAirment:[STATe]
driver.source.iq.impairment.set_state(state = False)
```

Activates/ deactivates the three impairment or correction values LEAKage, QUADrature and IQRatio for the baseband signal prior to input into the I/Q modulator.

**param state**  
1| ON| 0| OFF

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.iq.impairment.clone()
```

## Subgroups

### 6.7.5.1.1 IqRatio

#### SCPI Command :

```
[SOURce<HW>]:IQ:IMPairment:IQRatio:[MAGNitude]
```

#### class IqRatioCls

IqRatio commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_magnitude()** → float

```
# SCPI: [SOURce<HW>]:IQ:IMPairment:IQRatio:[MAGNitude]
value: float = driver.source.iq.impairment.iqRatio.get_magnitude()
```

Sets the ratio of I modulation to Q modulation (amplification ‘imbalance’). The input may be either in dB or %. The resolution is 0.001 dB, an input in percent is rounded to the closest valid value in dB. A query returns the value in dB.

**return**  
ipartq\_ratio: No help available

**set\_magnitude(ipartq\_ratio: float)** → None

```
# SCPI: [SOURce<HW>]:IQ:IMPairment:IQRatio:[MAGNitude]
driver.source.iq.impairment.iqRatio.set_magnitude(ipartq_ratio = 1.0)
```

Sets the ratio of I modulation to Q modulation (amplification ‘imbalance’). The input may be either in dB or %. The resolution is 0.001 dB, an input in percent is rounded to the closest valid value in dB. A query returns the value in dB.

**param ipartq\_ratio**  
float Range: -1 to 1

### 6.7.5.1.2 Leakage

#### SCPI Commands :

```
[SOURce<HW>]:IQ:IMPairment:LEAKage:I
[SOURce<HW>]:IQ:IMPairment:LEAKage:Q
```

#### class LeakageCls

Leakage commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_icomponent()** → float

```
# SCPI: [SOURCE<HW>]:IQ:IMPAIrmEnt:LEAKage:I
value: float = driver.source.iq.impaIrmEnt.leAKage.get_icomponent()
```

Sets the carrier leakage amplitude for the I-signal component.

**return**

ipart: No help available

**get\_qcomponent()** → float

```
# SCPI: [SOURCE<HW>]:IQ:IMPAIrmEnt:LEAKage:Q
value: float = driver.source.iq.impaIrmEnt.leAKage.get_qcomponent()
```

Sets the carrier leakage amplitude for the Q-signal component.

**return**

qpart: No help available

**set\_icomponent(ipart: float)** → None

```
# SCPI: [SOURCE<HW>]:IQ:IMPAIrmEnt:LEAKage:I
driver.source.iq.impaIrmEnt.leAKage.set_icomponent(ipart = 1.0)
```

Sets the carrier leakage amplitude for the I-signal component.

**param ipart**

float Range: -10 to 10

**set\_qcomponent(qpart: float)** → None

```
# SCPI: [SOURCE<HW>]:IQ:IMPAIrmEnt:LEAKage:Q
driver.source.iq.impaIrmEnt.leAKage.set_qcomponent(qpart = 1.0)
```

Sets the carrier leakage amplitude for the Q-signal component.

**param qpart**

float Range: -10 to 10

### 6.7.5.1.3 Quadrature

#### SCPI Command :

```
[SOURCE<HW>]:IQ:IMPAIrmEnt:QUADrature:[ANGLE]
```

#### class QuadratureCls

Quadrature commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_angle()** → float

```
# SCPI: [SOURCE<HW>]:IQ:IMPAIrmEnt:QUADrature:[ANGLE]
value: float = driver.source.iq.impaIrmEnt.quADrature.get_angle()
```

Sets the quadrature offset for the digital I/Q signal.

**return**  
angle: float Range: -10 to 10

**set\_angle**(angle: float) → None

```
# SCPI: [SOURCE<HW>]:IQ:IMPairment:QUADrature:[ANGLE]
driver.source.iq.impairment.quadrature.set_angle(angle = 1.0)
```

Sets the quadrature offset for the digital I/Q signal.

**param angle**  
float Range: -10 to 10

#### 6.7.5.1.4 Swap

**SCPI Command :**

```
[SOURCE<HW>]:IQ:IMPairment:SWAP:[STATE]
```

**class SwapCls**

Swap commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_state**() → bool

```
# SCPI: [SOURCE<HW>]:IQ:IMPairment:SWAP:[STATE]
value: bool = driver.source.iq.impairment.swap.get_state()
```

When set to ON, this command swaps the I and Q channel for an external modulation signal.

**return**  
state: 1| ON| 0| OFF

**set\_state**(state: bool) → None

```
# SCPI: [SOURCE<HW>]:IQ:IMPairment:SWAP:[STATE]
driver.source.iq.impairment.swap.set_state(state = False)
```

When set to ON, this command swaps the I and Q channel for an external modulation signal.

**param state**  
1| ON| 0| OFF

### 6.7.6 Loscillator

**SCPI Command :**

```
[SOURCE<HW>]:LOScillator:SOURce
```

**class LoscillatorCls**

Loscillator commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_source**() → SourceInt

```
# SCPI: [SOURCE<HW>]:LOSCillator:SOURce
value: enums.SourceInt = driver.source.loscillator.get_source()
```

Selects the source of the local oscillator signal.

**return**  
 source: INTERNAL| EXTERNAL INT: use built in oscillator; EXT: use signal at [LO/ REF IN] connector

**set\_source**(source: SourceInt) → None

```
# SCPI: [SOURCE<HW>]:LOSCillator:SOURce
driver.source.loscillator.set_source(source = enums.SourceInt.EXTERNAL)
```

Selects the source of the local oscillator signal.

**param source**  
 INTERNAL| EXTERNAL INT: use built in oscillator; EXT: use signal at [LO/ REF IN] connector

## 6.7.7 Phase

### SCPI Command :

```
[SOURCE<HW>]:PHASe
```

#### class PhaseCls

Phase commands group definition. 2 total commands, 1 Subgroups, 1 group commands

**get\_value**() → float

```
# SCPI: [SOURCE<HW>]:PHASe
value: float = driver.source.phase.get_value()
```

Specifies the phase variation relative to the current phase.

**return**  
 phase: float Range: -360 to 360, Unit: DEG

**set\_value**(phase: float) → None

```
# SCPI: [SOURCE<HW>]:PHASe
driver.source.phase.set_value(phase = 1.0)
```

Specifies the phase variation relative to the current phase.

**param phase**  
 float Range: -360 to 360, Unit: DEG

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.phase.clone()
```

## Subgroups

### 6.7.7.1 Reference

#### SCPI Command :

```
[SOURce<HW>]:PHASe:REFeRence
```

#### class ReferenceCls

Reference commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**set()** → None

```
# SCPI: [SOURce<HW>]:PHASe:REFeRence
driver.source.phase.reference.set()
```

Adopts the phase set with command [:SOURce]:PHASe as the current phase.

**set\_with\_opc**(opc\_timeout\_ms: int = -1) → None

```
# SCPI: [SOURce<HW>]:PHASe:REFeRence
driver.source.phase.reference.set_with_opc()
```

Adopts the phase set with command [:SOURce]:PHASe as the current phase.

Same as set, but waits for the operation to complete before continuing further. Use the RsSgt.utilities.opc\_timeout\_set() to set the timeout value.

**param opc\_timeout\_ms**

Maximum time to wait in milliseconds, valid only for this call.

## 6.7.8 Power

#### SCPI Commands :

```
[SOURce<HW>]:POWer:LMODe
[SOURce<HW>]:POWer:PEP
[SOURce<HW>]:POWer:POWer
[SOURce<HW>]:POWer:SCHaracteristic
```

#### class PowerCls

Power commands group definition. 24 total commands, 6 Subgroups, 4 group commands

**get\_lmode()** → PowLevMode

```
# SCPI: [SOURce<HW>]:POWer:LMODe
value: enums.PowLevMode = driver.source.power.get_lmode()
```

Selects the level mode.

```
return
    lev_mode: NORMal| LOWNoise| LOWDistortion NORM automatic selection of the
    best settings LNOISE settings for lowest noise LDISortion settings for lowest distortions
```

**get\_pep()** → float

```
# SCPI: [SOURCE<HW>]:POWER:PEP
value: float = driver.source.power.get_pep()
```

Queries the RF signal peak envelope power.

```
return
    pep: float
```

**get\_power()** → float

```
# SCPI: [SOURCE<HW>]:POWER:POWER
value: float = driver.source.power.get_power()
```

Sets the level at the RF output connector. This value does not consider a specified offset. The command [:SOURCE]:POWER[:LEVel][:IMMediate][:AMPLitude] sets the level of the ‘Level’ display, that means the level containing offset.

```
return
    amplitude: float Range: -20 to 25
```

**get\_scharacteristic()** → PowLevBehaviour

```
# SCPI: [SOURCE<HW>]:POWER:SCharacteristic
value: enums.PowLevBehaviour = driver.source.power.get_scharacteristic()
```

Selects the characteristic for the level setting.

```
return
    characteristic: AUTO| UNINinterrupted| CVSWr| USER| MONotone UNINinterrupted
    uninterrupted level setting CVSWr constant-VSWR MONotone strictly monotone
```

**set\_lmode(lev\_mode: PowLevMode)** → None

```
# SCPI: [SOURCE<HW>]:POWER:LMODe
driver.source.power.set_lmode(lev_mode = enums.PowLevMode.LOWDistortion)
```

Selects the level mode.

```
param lev_mode
    NORMal| LOWNoise| LOWDistortion NORM automatic selection of the best settings
    LNOISE settings for lowest noise LDISortion settings for lowest distortions
```

**set\_power(amplitude: float)** → None

```
# SCPI: [SOURCE<HW>]:POWER:POWER
driver.source.power.set_power(amplitude = 1.0)
```

Sets the level at the RF output connector. This value does not consider a specified offset. The command [:SOURCE]:POWER[:LEVel][:IMMediate][:AMPLitude] sets the level of the ‘Level’ display, that means the level containing offset.

**param amplitude**

float Range: -20 to 25

**set\_scharacteristic**(characteristic: *PowLevBehaviour*) → None

```
# SCPI: [SOURCE<HW>]:POWER:SCharacteristic
driver.source.power.set_scharacteristic(characteristic = enums.PowLevBehaviour.
↳ AUTO)
```

Selects the characteristic for the level setting.

**param characteristic**AUTO| UNINterrupted| CVSWr| USER| MONotone UNINterrupted uninterruptd  
level setting CVSWr constant-VSWR MONotone strictly monotone

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.clone()
```

## Subgroups

### 6.7.8.1 Alc

#### SCPI Commands :

```
[SOURCE<HW>]:POWER:ALC:DSEnsitivity
[SOURCE<HW>]:POWER:ALC:[STATE]
```

**class AlcCls**

Alc commands group definition. 3 total commands, 1 Subgroups, 2 group commands

**get\_dsensitivity**() → CalPowDetAtt

```
# SCPI: [SOURCE<HW>]:POWER:ALC:DSEnsitivity
value: enums.CalPowDetAtt = driver.source.power.alc.get_dsensitivity()
```

Sets the power detector sensitivity. Used for compatibility reasons only.

**return**

sensitivity: OFF| LOW| MED| HIGH

**get\_state**() → PowAlcState

```
# SCPI: [SOURCE<HW>]:POWER:ALC:[STATE]
value: enums.PowAlcState = driver.source.power.alc.get_state()
```

Activates/deactivates automatic level control.

**return**

state: 1| OFFTable| OFF| ONTable| AUTO| ON



**set\_dsensitivity**(*sensitivity: CalPowDetAtt*) → None

```
# SCPI: [SOURCE<HW>]:POWER:ALC:DSensitivity
driver.source.power.alc.set_dsensitivity(sensitivity = enums.CalPowDetAtt.HIGH)
```

Sets the power detector sensitivity. Used for compatibility reasons only.

**param sensitivity**  
OFF| LOW| MED| HIGH

**set\_state**(*state: PowAlcState*) → None

```
# SCPI: [SOURCE<HW>]:POWER:ALC:[STATE]
driver.source.power.alc.set_state(state = enums.PowAlcState._1)
```

Activates/deactivates automatic level control.

**param state**  
1| OFFTable| OFF| ONTable| AUTO| ON

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.alc.clone()
```

## Subgroups

### 6.7.8.1.1 Sonce

#### SCPI Command :

```
[SOURCE<HW>]:POWER:ALC:SONCe
```

#### class SonceCls

Sonce commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**set**() → None

```
# SCPI: [SOURCE<HW>]:POWER:ALC:SONCe
driver.source.power.alc.sonce.set()
```

Briefly activates level control for correction purposes.

**set\_with\_opc**(*opc\_timeout\_ms: int = -1*) → None

```
# SCPI: [SOURCE<HW>]:POWER:ALC:SONCe
driver.source.power.alc.sonce.set_with_opc()
```

Briefly activates level control for correction purposes.

Same as set, but waits for the operation to complete before continuing further. Use the RsSgt.utilities.opc\_timeout\_set() to set the timeout value.

**param opc\_timeout\_ms**  
Maximum time to wait in milliseconds, valid only for this call.

### 6.7.8.2 Attenuation

#### SCPI Command :

```
[SOURce<HW>]:POWer:ATTenuation:DIGital
```

#### class AttenuationCls

Attenuation commands group definition. 3 total commands, 2 Subgroups, 1 group commands

**get\_digital()** → float

```
# SCPI: [SOURce<HW>]:POWer:ATTenuation:DIGital
value: float = driver.source.power.attenuation.get_digital()
```

Sets a relative attenuation value for the baseband signal.

**return**

att\_digital: float Range: 0 to 80, Unit: dB

**set\_digital(att\_digital: float)** → None

```
# SCPI: [SOURce<HW>]:POWer:ATTenuation:DIGital
driver.source.power.attenuation.set_digital(att_digital = 1.0)
```

Sets a relative attenuation value for the baseband signal.

**param att\_digital**

float Range: 0 to 80, Unit: dB

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.attenuation.clone()
```

#### Subgroups

### 6.7.8.2.1 RfOff

#### SCPI Command :

```
[SOURce<HW>]:POWer:ATTenuation:RFOff:MODE
```

#### class RfOffCls

RfOff commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_mode()** → PowRfOffMode

```
# SCPI: [SOURce<HW>]:POWer:ATTenuation:RFOff:MODE
value: enums.PowRfOffMode = driver.source.power.attenuation.rfOff.get_mode()
```

Determines the attenuator's state after the instrument is switched on.

**return**

mode: MAX| FATTenuated| FIXed| UNCHanged MAX = FATTenuated Sets attenuation to maximum when the RF signal is switched off. This setting is recommended for applications that require a high level of noise suppression. FIXed = UNCHanged Retains the current setting and keeps the output impedance constant during RF off.

**set\_mode**(mode: *PowRfOffMode*) → None

```
# SCPI: [SOURCE<HW>]:POWER:ATTenuation:RFOff:MODE
driver.source.power.attenuation.rfOff.set_mode(mode = enums.PowRfOffMode.FIXed)
```

Determines the attenuator's state after the instrument is switched on.

**param mode**

MAX| FATTenuated| FIXed| UNCHanged MAX = FATTenuated Sets attenuation to maximum when the RF signal is switched off. This setting is recommended for applications that require a high level of noise suppression. FIXed = UNCHanged Retains the current setting and keeps the output impedance constant during RF off.

**6.7.8.2.2 Sover****SCPI Command :**

```
[SOURCE<HW>]:POWER:ATTenuation:SOVer:[OFFSet]
```

**class SoverCls**

Sover commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_offset**() → float

```
# SCPI: [SOURCE<HW>]:POWER:ATTenuation:SOVer:[OFFSet]
value: float = driver.source.power.attenuation.sover.get_offset()
```

Sets the switch-over offset value of the attenuator.

**return**

offset: float Range: -10 to 10

**set\_offset**(offset: *float*) → None

```
# SCPI: [SOURCE<HW>]:POWER:ATTenuation:SOVer:[OFFSet]
driver.source.power.attenuation.sover.set_offset(offset = 1.0)
```

Sets the switch-over offset value of the attenuator.

**param offset**

float Range: -10 to 10

### 6.7.8.3 Level

#### class LevelCls

Level commands group definition. 3 total commands, 1 Subgroups, 0 group commands

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.level.clone()
```

#### Subgroups

##### 6.7.8.3.1 Immediate

#### SCPI Commands :

```
[SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:OFFSet
[SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:RCL
[SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:[AMPLitude]
```

#### class ImmediateCls

Immediate commands group definition. 3 total commands, 0 Subgroups, 3 group commands

**get\_amplitude()** → float

```
# SCPI: [SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:[AMPLitude]
value: float = driver.source.power.level.immediate.get_amplitude()
```

Sets the RF level at the RF output connector of the instrument.

**return**  
amplitude: float Range: -120 to 25, Unit: dBm

**get\_offset()** → float

```
# SCPI: [SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:OFFSet
value: float = driver.source.power.level.immediate.get_offset()
```

Specifies the constant level offset of a downstream attenuator/amplifier. If a level offset is entered, the level entered with POWER no longer corresponds to the RF output level. The following correlation applies: POWER = RF output level + POWER:OFFSet. Entering a level offset does not change the RF output level, but rather the query value of POWER. Only dB is permitted as the unit here. The linear units (V, W, etc.) are not permitted.

**return**  
offset: float Range: -100 to 100

**get\_recall()** → InclExcl

```
# SCPI: [SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:RCL
value: enums.InclExcl = driver.source.power.level.immediate.get_recall()
```

No command help available

**return**  
 rcl\_excl\_pow: No help available

**set\_amplitude**(*amplitude: float*) → None

```
# SCPI: [SOURCE<HW>]:POWER:[LEVEL]:[IMMEDIATE]:[AMPLITUDE]
driver.source.power.level.immediate.set_amplitude(amplitude = 1.0)
```

Sets the RF level at the RF output connector of the instrument.

**param amplitude**  
 float Range: -120 to 25, Unit: dBm

**set\_offset**(*offset: float*) → None

```
# SCPI: [SOURCE<HW>]:POWER:[LEVEL]:[IMMEDIATE]:OFFSet
driver.source.power.level.immediate.set_offset(offset = 1.0)
```

Specifies the constant level offset of a downstream attenuator/amplifier. If a level offset is entered, the level entered with POWER no longer corresponds to the RF output level. The following correlation applies: POWER = RF output level + POWER:OFFSet. Entering a level offset does not change the RF output level, but rather the query value of POWER. Only dB is permitted as the unit here. The linear units (V, W, etc.) are not permitted.

**param offset**  
 float Range: -100 to 100

**set\_recall**(*rcl\_excl\_pow: InclExcl*) → None

```
# SCPI: [SOURCE<HW>]:POWER:[LEVEL]:[IMMEDIATE]:RCL
driver.source.power.level.immediate.set_recall(rcl_excl_pow = enums.InclExcl.
↳EXCLUDE)
```

No command help available

**param rcl\_excl\_pow**  
 No help available

#### 6.7.8.4 Limit

##### SCPI Command :

```
[SOURCE<HW>]:POWER:LIMit:[AMPLitude]
```

##### class LimitCls

Limit commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_amplitude**() → float

```
# SCPI: [SOURCE<HW>]:POWER:LIMit:[AMPLitude]
value: float = driver.source.power.limit.get_amplitude()
```

Sets the upper limit of the RF signal power. An instrument preset does not affect this value. A factory preset (method RsSgt.System.Fpreset.set) sets the specified factory upper limit value.

**return**  
 amplitude: float Range: -120 to 25

**set\_amplitude**(*amplitude: float*) → None

```
# SCPI: [SOURCE<HW>]:POWER:LIMit:[AMPLitude]
driver.source.power.limit.set_amplitude(amplitude = 1.0)
```

Sets the upper limit of the RF signal power. An instrument preset does not affect this value. A factory preset (method RsSgt.System.Fpreset.set) sets the specified factory upper limit value.

**param amplitude**  
float Range: -120 to 25

### 6.7.8.5 Range

#### SCPI Commands :

```
[SOURCE<HW>]:POWER:RANge:LOWer
[SOURCE<HW>]:POWER:RANge:UPPer
```

#### class RangeCls

Range commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_lower**() → float

```
# SCPI: [SOURCE<HW>]:POWER:RANge:LOWer
value: float = driver.source.power.range.get_lower()
```

Queries the minimum/maximum level range in the current level mode

**return**  
lower: float

**get\_upper**() → float

```
# SCPI: [SOURCE<HW>]:POWER:RANge:UPPer
value: float = driver.source.power.range.get_upper()
```

Queries the minimum/maximum level range in the current level mode

**return**  
upper: float

### 6.7.8.6 Servoing

#### SCPI Commands :

```
[SOURCE<HW>]:POWER:SERVoing:SET
[SOURCE<HW>]:POWER:SERVoing:STATe
[SOURCE<HW>]:POWER:SERVoing:TARGet
[SOURCE<HW>]:POWER:SERVoing:TEST
[SOURCE<HW>]:POWER:SERVoing:TOLerance
[SOURCE<HW>]:POWER:SERVoing:TRACking
```

**class ServoingCls**

Servoing commands group definition. 8 total commands, 1 Subgroups, 6 group commands

**class SetStruct**

Structure for reading output parameters. Fields:

- Target: float: float Starts a single power servoing setting cycle, see ‘About power servoing’. Sets the desired output power level required at the DUT, see[:SOURce]:POWER:SERVoing:TARGet.
- Start: enums.Test: 0| 1| RUNning| STOPped Queries the current status of the powerservoing procedure. 0|RUNning Procedure is ok and or running without errors. 1|STOPped Procedure is stopped due to an error.

**get\_set()** → SetStruct

```
# SCPI: [SOURce<HW>]:POWER:SERVoing:SET
value: SetStruct = driver.source.power.servoing.get_set()
```

Sets the target output power level and queries power servoing procedure status.

**return**

structure: for return value, see the help for SetStruct structure arguments.

**get\_state()** → bool

```
# SCPI: [SOURce<HW>]:POWER:SERVoing:STATE
value: bool = driver.source.power.servoing.get_state()
```

Activates/deactivates power servoing.

**return**

state: 1| ON| 0| OFF

**get\_target()** → float

```
# SCPI: [SOURce<HW>]:POWER:SERVoing:TARGet
value: float = driver.source.power.servoing.get_target()
```

Sets the target output power level required at the DUT.

**return**

target\_level: float Range: -120 to 25

**get\_test()** → Test

```
# SCPI: [SOURce<HW>]:POWER:SERVoing:TEST
value: enums.Test = driver.source.power.servoing.get_test()
```

Queries the state of the power servoing procedure.

**return**

start: 0| 1| RUNning| STOPped

**get\_tolerance()** → float

```
# SCPI: [SOURce<HW>]:POWER:SERVoing:TOLerance
value: float = driver.source.power.servoing.get_tolerance()
```

Sets the tolerance level interval, in which the ‘Target’ output power level of the DUT lies. A large tolerance accelerates the power servoing procedure but also reduces the accuracy of the target output power level.

**return**

tolerance: float Range: 0.01 to 3

**get\_tracking()** → bool

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:TRACking
value: bool = driver.source.power.servoing.get_tracking()
```

Activates/deactivates level tracking. Activation increases measurement accuracy but also measurement time.

**return**

state: 1| ON| 0| OFF

**set\_state(state: bool)** → None

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:STATe
driver.source.power.servoing.set_state(state = False)
```

Activates/deactivates power servoing.

**param state**

1| ON| 0| OFF

**set\_target(target\_level: float)** → None

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:TARGeT
driver.source.power.servoing.set_target(target_level = 1.0)
```

Sets the target output power level required at the DUT.

**param target\_level**

float Range: -120 to 25

**set\_tolerance(tolerance: float)** → None

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:TOLerance
driver.source.power.servoing.set_tolerance(tolerance = 1.0)
```

Sets the tolerance level interval, in which the ‘Target’ output power level of the DUT lies. A large tolerance accelerates the power servoing procedure but also reduces the accuracy of the target output power level.

**param tolerance**

float Range: 0.01 to 3

**set\_tracking(state: bool)** → None

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:TRACking
driver.source.power.servoing.set_tracking(state = False)
```

Activates/deactivates level tracking. Activation increases measurement accuracy but also measurement time.

**param state**

1| ON| 0| OFF



## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.serving.clone()
```

## Subgroups

### 6.7.8.6.1 Sensor

#### SCPI Commands :

```
[SOURCE<HW>]:POWER:SERVoing:SENSor:APERture
[SOURCE<HW>]:POWER:SERVoing:SENSor
```

#### class SensorCls

Sensor commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_aperture()** → float

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:SENSor:APERture
value: float = driver.source.power.serving.sensor.get_aperture()
```

Sets the aperture time (size of the acquisition interval) of the power sensor during power serving.

```
return
    aperture: float Range: 10e-6 to 100e-3
```

**get\_value()** → PowSensWithUndef

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:SENSor
value: enums.PowSensWithUndef = driver.source.power.serving.sensor.get_value()
```

Sets the power sensor as mapped with the remote command SLIST:ELEMENT<ch>:MAPPING.

```
return
    sensor: SENS1| SENS2| SENSor2| SENS3| SENSor3| SENS4| SENSor4| SENSor1|
    UNDEFINED
```

**set\_aperture(aperture: float)** → None

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:SENSor:APERture
driver.source.power.serving.sensor.set_aperture(aperture = 1.0)
```

Sets the aperture time (size of the acquisition interval) of the power sensor during power serving.

```
param aperture
    float Range: 10e-6 to 100e-3
```

**set\_value(sensor: PowSensWithUndef)** → None

```
# SCPI: [SOURCE<HW>]:POWER:SERVoing:SENSor
driver.source.power.serving.sensor.set_value(sensor = enums.PowSensWithUndef.
↳ SENS1)
```

Sets the power sensor as mapped with the remote command SLIST:ELEMENT<ch>:MAPPING.

**param sensor**

SENS1| SENS2| SENSor2| SENS3| SENSor3| SENS4| SENSor4| SENSor1| UNDe-  
fined

## 6.7.9 Roscillator

**SCPI Command :**

[SOURCE<HW>]:ROSCillator:SOURce

**class RoscillatorCls**

Roscillator commands group definition. 3 total commands, 2 Subgroups, 1 group commands

**get\_source()** → SourceInt

```
# SCPI: [SOURCE<HW>]:ROSCillator:SOURce
value: enums.SourceInt = driver.source.roscillator.get_source()
```

Select the reference oscillator signal source.

**return**

source: INTernal| EXTernal

**set\_source(source: SourceInt)** → None

```
# SCPI: [SOURCE<HW>]:ROSCillator:SOURce
driver.source.roscillator.set_source(source = enums.SourceInt.EXTernal)
```

Select the reference oscillator signal source.

**param source**

INTernal| EXTernal

### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.roscillator.clone()
```

### Subgroups

#### 6.7.9.1 External

**SCPI Command :**

[SOURCE<HW>]:ROSCillator:EXTernal:FREQuency

**class ExternalCls**

External commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_frequency()** → RoscFreqExt

```
# SCPI: [SOURCE<HW>]:ROSCillator:EXTernal:FREQuency
value: enums.RoscFreqExt = driver.source.roscillator.external.get_frequency()
```

Selects the frequency of the external reference.

#### return

ext\_freq: 10MHZ| 100MHZ| 1000MHZ| 13MHZ 13MHZ requires RF board with part number 1419.5308.02. To find out the RF board installed in the instrument: Select 'SGMA-GUI instrument name Setup Hardware Config' 'RF Assembly' Observe the part number of the assembly 'RfBoard'.

**set\_frequency**(ext\_freq: RoscFreqExt) → None

```
# SCPI: [SOURCE<HW>]:ROSCillator:EXTernal:FREQuency
driver.source.roscillator.external.set_frequency(ext_freq = enums.RoscFreqExt._
↪1000MHZ)
```

Selects the frequency of the external reference.

#### param ext\_freq

10MHZ| 100MHZ| 1000MHZ| 13MHZ 13MHZ requires RF board with part number 1419.5308.02. To find out the RF board installed in the instrument: Select 'SGMA-GUI instrument name Setup Hardware Config' 'RF Assembly' Observe the part number of the assembly 'RfBoard'.

## 6.7.9.2 Output

### SCPI Command :

```
[SOURCE<HW>]:ROSCillator:OUTPut:FREQuency
```

#### class OutputCls

Output commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_frequency**() → RoscFreqExt

```
# SCPI: [SOURCE<HW>]:ROSCillator:OUTPut:FREQuency
value: enums.RoscFreqExt = driver.source.roscillator.output.get_frequency()
```

Selects the output for the reference oscillator signal.

#### return

output\_freq: 10MHZ| 100MHZ| 1000MHZ| 13MHZ 13MHZ requires RF board with part number 1419.5308.02.

**set\_frequency**(output\_freq: RoscFreqExt) → None

```
# SCPI: [SOURCE<HW>]:ROSCillator:OUTPut:FREQuency
driver.source.roscillator.output.set_frequency(output_freq = enums.RoscFreqExt._
↪1000MHZ)
```

Selects the output for the reference oscillator signal.

#### param output\_freq

10MHZ| 100MHZ| 1000MHZ| 13MHZ 13MHZ requires RF board with part number 1419.5308.02.

## 6.8 Status

### SCPI Command :

STATus:PRESet

#### class StatusCls

Status commands group definition. 22 total commands, 3 Subgroups, 1 group commands

**get\_preset()** → str

```
# SCPI: STATus:PRESet
value: str = driver.status.get_preset()
```

Resets the status registers. All PTRansition parts are set to FFFFh (32767) , i.e. all transitions from 0 to 1 are detected. All NTRansition parts are set to 0, i.e. a transition from 1 to 0 in a CONDition bit is not detected. The ENABLE parts of STATus:OPERation and STATus:QUEStionable are set to 0, i.e. all events in these registers are not passed on.

**return**  
preset: string

**set\_preset(preset: str)** → None

```
# SCPI: STATus:PRESet
driver.status.set_preset(preset = 'abc')
```

Resets the status registers. All PTRansition parts are set to FFFFh (32767) , i.e. all transitions from 0 to 1 are detected. All NTRansition parts are set to 0, i.e. a transition from 1 to 0 in a CONDition bit is not detected. The ENABLE parts of STATus:OPERation and STATus:QUEStionable are set to 0, i.e. all events in these registers are not passed on.

**param preset**  
string

### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.clone()
```

### Subgroups

#### 6.8.1 Operation

### SCPI Commands :

STATus:OPERation:CONDition  
STATus:OPERation:ENABLE  
STATus:OPERation:NTRansition  
STATus:OPERation:PTRansition  
STATus:OPERation:[EVENTt]

**class OperationCls**

Operation commands group definition. 10 total commands, 1 Subgroups, 5 group commands

**get\_condition()** → str

```
# SCPI: STATus:OPERation:CONDition
value: str = driver.status.operation.get_condition()
```

Queries the content of the CONDition part of the STATus:OPERation register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out because it indicates the current hardware status.

```
return
    condition: string
```

**get\_enable()** → str

```
# SCPI: STATus:OPERation:ENABLE
value: str = driver.status.operation.get_enable()
```

Sets the bits of the ENABLE part of the STATus:OPERation register. This setting determines which events of the Status-Event part are forwarded to the sum bit in the status byte. These events can be used for a service request.

```
return
    enable: string
```

**get\_event()** → str

```
# SCPI: STATus:OPERation:[EVENTt]
value: str = driver.status.operation.get_event()
```

Queries the content of the EVENT part of the STATus:OPERation register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

```
return
    value: No help available
```

**get\_ntransition()** → str

```
# SCPI: STATus:OPERation:NTRansition
value: str = driver.status.operation.get_ntransition()
```

Sets the bits of the NTRansition part of the STATus:OPERation register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register. The disappearance of an event in the hardware is thus registered, for example the end of an adjustment.

```
return
    ntransition: string
```

**get\_ptransition()** → str

```
# SCPI: STATus:OPERation:PTRansition
value: str = driver.status.operation.get_ptransition()
```

Sets the bits of the PTRansition part of the STATus:OPERation register. If a bit is set, a transition from 0 to 1 in the condition part causes an entry to be made in the EVENT part of the register. A new event in the hardware is thus registered, for example the start of an adjustment.

**return**  
ptransition: string

**set\_enable**(enable: str) → None

```
# SCPI: STATus:OPERation:ENABLe
driver.status.operation.set_enable(enable = 'abc')
```

Sets the bits of the ENABLe part of the STATus:OPERation register. This setting determines which events of the Status-Event part are forwarded to the sum bit in the status byte. These events can be used for a service request.

**param enable**  
string

**set\_event**(value: str) → None

```
# SCPI: STATus:OPERation:[EVENTt]
driver.status.operation.set_event(value = 'abc')
```

Queries the content of the EVENTt part of the STATus:OPERation register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENTt part is deleted after being read out.

**param value**  
string

**set\_ntransition**(ntransition: str) → None

```
# SCPI: STATus:OPERation:NTRansition
driver.status.operation.set_ntransition(ntransition = 'abc')
```

Sets the bits of the NTRansition part of the STATus:OPERation register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENTt part of the register. The disappearance of an event in the hardware is thus registered, for example the end of an adjustment.

**param ntransition**  
string

**set\_ptransition**(ptransition: str) → None

```
# SCPI: STATus:OPERation:PTRansition
driver.status.operation.set_ptransition(ptransition = 'abc')
```

Sets the bits of the PTRansition part of the STATus:OPERation register. If a bit is set, a transition from 0 to 1 in the condition part causes an entry to be made in the EVENTt part of the register. A new event in the hardware is thus registered, for example the start of an adjustment.

**param ptransition**  
string

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.operation.clone()
```

## Subgroups

### 6.8.1.1 Bit<BitNumberNull>

#### RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.status.operation.bit.repcap_bitNumberNull_get()
driver.status.operation.bit.repcap_bitNumberNull_set(repcap.BitNumberNull.Nr0)
```

#### class BitCls

Bit commands group definition. 5 total commands, 5 Subgroups, 0 group commands Repeated Capability: BitNumberNull, default value after init: BitNumberNull.Nr0

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.operation.bit.clone()
```

## Subgroups

### 6.8.1.1.1 Condition

#### SCPI Command :

```
STATUS:OPERation:BIT<BITNR>:CONDition
```

#### class ConditionCls

Condition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATUS:OPERation:BIT<BITNR>:CONDition
value: str = driver.status.operation.bit.condition.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

#### param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

#### return

condition: No help available

### 6.8.1.1.2 Enable

#### SCPI Command :

```
STATus:OPERation:BIT<BITNR>:ENABle
```

#### class EnableCls

Enable commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:ENABle
value: str = driver.status.operation.bit.enable.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

**return**

enable: No help available

**set**(*enable: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:OPERation:BIT<BITNR>:ENABle
driver.status.operation.bit.enable.set(enable = 'abc', bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

**param enable**

No help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

### 6.8.1.1.3 Event

#### SCPI Command :

```
STATus:OPERation:BIT<BITNR>:[EVENT]
```

#### class EventCls

Event commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:[EVENT]
value: str = driver.status.operation.bit.event.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')



**return**  
event: No help available

#### 6.8.1.1.4 Ntransition

##### SCPI Command :

```
STATUS:OPERation:BIT<BITNR>:NTRansition
```

##### class NtransitionCls

Ntransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATUS:OPERation:BIT<BITNR>:NTRansition
value: str = driver.status.operation.bit.ntransition.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

**param bitNumberNull**  
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

**return**  
ntransition: No help available

**set**(*ntransition: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATUS:OPERation:BIT<BITNR>:NTRansition
driver.status.operation.bit.ntransition.set(ntransition = 'abc', bitNumberNull_
↳ = repcap.BitNumberNull.Default)
```

No command help available

**param ntransition**  
No help available

**param bitNumberNull**  
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

#### 6.8.1.1.5 Ptransition

##### SCPI Command :

```
STATUS:OPERation:BIT<BITNR>:PTRansition
```

##### class PtransitionCls

Ptransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATUS:OPERation:BIT<BITNR>:PTRansition
value: str = driver.status.operation.bit.ptransition.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

**return**

ptransition: No help available

**set**(ptransition: str, bitNumberNull=BitNumberNull.Default) → None

```
# SCPI: STATus:OPERation:BIT<BITNR>:PTRansition
driver.status.operation.bit.ptransition.set(ptransition = 'abc', bitNumberNull=
↪= repcap.BitNumberNull.Default)
```

No command help available

**param ptransition**

No help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

## 6.8.2 Questionable

### SCPI Commands :

```
STATus:QUEStionable:CONDition
STATus:QUEStionable:ENABle
STATus:QUEStionable:NTRansition
STATus:QUEStionable:PTRansition
STATus:QUEStionable:[EVENTt]
```

#### class QuestionableCls

Questionable commands group definition. 10 total commands, 1 Subgroups, 5 group commands

**get\_condition()** → str

```
# SCPI: STATus:QUEStionable:CONDition
value: str = driver.status.questionable.get_condition()
```

Queries the content of the CONDition part of the STATus:QUEStionable register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out since it indicates the current hardware status.

**return**

condition: string

**get\_enable()** → str

```
# SCPI: STATus:QUEStionable:ENABle
value: str = driver.status.questionable.get_enable()
```

Sets the bits of the ENABle part of the STATus:QUEStionable register. The enable part determines which events of the STATus:EVENTt part are enabled for the summary bit in the status byte. These events can be used for a service request. If a bit in the ENABle part is 1, and the corresponding EVENTt bit is true, a positive transition occurs in the summary bit. This transition is reported to the next higher level.

**return**  
enable: string

**get\_event()** → str

```
# SCPI: STATUS:QUESTIONable:EVENTt
value: str = driver.status.questionable.get_event()
```

Queries the content of the EVENT part of the method RsSgt.Status.Questionable.event register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

**return**  
value: No help available

**get\_ntransition()** → str

```
# SCPI: STATUS:QUESTIONable:NTRansition
value: str = driver.status.questionable.get_ntransition()
```

Sets the bits of the NTRansition part of the STATUS:QUESTIONable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

**return**  
ntransition: string

**get\_ptransition()** → str

```
# SCPI: STATUS:QUESTIONable:PTRansition
value: str = driver.status.questionable.get_ptransition()
```

Sets the bits of the NTRansition part of the STATUS:QUESTIONable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

**return**  
ptransition: string

**set\_condition(condition: str)** → None

```
# SCPI: STATUS:QUESTIONable:CONDITION
driver.status.questionable.set_condition(condition = 'abc')
```

Queries the content of the CONDITION part of the STATUS:QUESTIONable register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out since it indicates the current hardware status.

**param condition**  
string

**set\_enable(enable: str)** → None

```
# SCPI: STATUS:QUESTIONable:ENABLE
driver.status.questionable.set_enable(enable = 'abc')
```

Sets the bits of the ENABLE part of the STATUS:QUESTIONable register. The enable part determines which events of the STATUS:EVENT part are enabled for the summary bit in the status byte. These events can be used for a service request. If a bit in the ENABLE part is 1, and the corresponding EVENT bit is true, a positive transition occurs in the summary bit. This transition is reported to the next higher level.

**param enable**  
string

**set\_event**(value: str) → None

```
# SCPI: STATus:QUESTionable:[EVENT]
driver.status.questionable.set_event(value = 'abc')
```

Queries the content of the EVENT part of the method RsSgt.Status.Questionable.event register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

**param value**  
string

**set\_ntransition**(ntransition: str) → None

```
# SCPI: STATus:QUESTionable:NTRansition
driver.status.questionable.set_ntransition(ntransition = 'abc')
```

Sets the bits of the NTRansition part of the STATus:QUESTionable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

**param ntransition**  
string

**set\_ptransition**(ptransition: str) → None

```
# SCPI: STATus:QUESTionable:PTRansition
driver.status.questionable.set_ptransition(ptransition = 'abc')
```

Sets the bits of the PTRansition part of the STATus:QUESTionable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

**param ptransition**  
string

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.questionable.clone()
```

## Subgroups

### 6.8.2.1 Bit<BitNumberNull>

#### RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.status.questionable.bit.repcap_bitNumberNull_get()
driver.status.questionable.bit.repcap_bitNumberNull_set(repcap.BitNumberNull.Nr0)
```

#### class BitCls

Bit commands group definition. 5 total commands, 5 Subgroups, 0 group commands Repeated Capability: BitNumberNull, default value after init: BitNumberNull.Nr0

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.questionable.bit.clone()
```

## Subgroups

### 6.8.2.1.1 Condition

#### SCPI Command :

```
STATus:QUEStionable:BIT<BITNR>:CONDition
```

#### class ConditionCls

Condition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:CONDition
value: str = driver.status.questionable.bit.condition.get(bitNumberNull =
↳repcap.BitNumberNull.Default)
```

No command help available

#### param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

#### return

condition: No help available

### 6.8.2.1.2 Enable

#### SCPI Command :

```
STATus:QUEStionable:BIT<BITNR>:ENABLE
```

#### class EnableCls

Enable commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:ENABLE
value: str = driver.status.questionable.bit.enable.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

#### param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

#### return

enable: No help available

**set**(enable: str, bitNumberNull=BitNumberNull.Default) → None

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:ENABle
driver.status.questionable.bit.enable.set(enable = 'abc', bitNumberNull = ↪
↪repcap.BitNumberNull.Default)
```

No command help available

**param enable**

No help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

### 6.8.2.1.3 Event

#### SCPI Command :

```
STATus:QUEStionable:BIT<BITNR>:[EVENTt]
```

#### class EventCls

Event commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:[EVENTt]
value: str = driver.status.questionable.bit.event.get(bitNumberNull = repcap.
↪BitNumberNull.Default)
```

No command help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

**return**

event: No help available

### 6.8.2.1.4 Ntransition

#### SCPI Command :

```
STATus:QUEStionable:BIT<BITNR>:NTRansition
```

#### class NtransitionCls

Ntransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:NTRansition
value: str = driver.status.questionable.bit.ntransition.get(bitNumberNull = ↪
↪repcap.BitNumberNull.Default)
```

No command help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

**return**

ntransition: No help available

**set**(ntransition: str, bitNumberNull=BitNumberNull.Default) → None

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:NTRansition
driver.status.questionable.bit.ntransition.set(ntransition = 'abc',
↪bitNumberNull = repcap.BitNumberNull.Default)
```

No command help available

**param ntransition**

No help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

**6.8.2.1.5 Ptransition****SCPI Command :**

```
STATus:QUEStionable:BIT<BITNR>:PTRansition
```

**class PtransitionCls**

Ptransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get**(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:PTRansition
value: str = driver.status.questionable.bit.ptransition.get(bitNumberNull =
↪repcap.BitNumberNull.Default)
```

No command help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

**return**

ptransition: No help available

**set**(ptransition: str, bitNumberNull=BitNumberNull.Default) → None

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:PTRansition
driver.status.questionable.bit.ptransition.set(ptransition = 'abc',
↪bitNumberNull = repcap.BitNumberNull.Default)
```

No command help available

**param ptransition**

No help available

**param bitNumberNull**

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

### 6.8.3 Queue

#### SCPI Command :

STATus:QUEue:[NEXT]

#### class QueueCls

Queue commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_next()** → str

```
# SCPI: STATus:QUEue:[NEXT]
value: str = driver.status.queue.get_next()
```

Queries the oldest entry in the error queue and then deletes it. Positive error numbers denote device-specific errors, and negative error numbers denote error messages defined by SCPI. If the error queue is empty, 0 ('No error') is returned. The command is identical to SYSTem:ERRor[:NEXT]?

```
return
    next_py: string
```

## 6.9 System

#### SCPI Commands :

SYSTem:DID  
SYSTem:PRESet  
SYSTem:PRESet:ALL  
SYSTem:PRESet:BASE  
SYSTem:RESet  
SYSTem:RESet:ALL  
SYSTem:RESet:BASE  
SYSTem:SREStore  
SYSTem:SSAVe  
SYSTem:TZONE  
SYSTem:VERSion

#### class SystemCls

System commands group definition. 43 total commands, 8 Subgroups, 11 group commands

**get\_did()** → str

```
# SCPI: SYSTem:DID
value: str = driver.system.get_did()
```

No command help available

```
return
    pseudo_string: No help available
```

**get\_tzone()** → str



```
# SCPI: SYSTem:TZONe
value: str = driver.system.get_tzone()
```

No command help available

```
return
pseudo_string: No help available
```

**get\_version()** → str

```
# SCPI: SYSTem:VERsion
value: str = driver.system.get_version()
```

Queries the SCPI version the instrument's command set complies with.

```
return
version: string
```

**preset(pseudo\_string: str)** → None

```
# SCPI: SYSTem:PRESet
driver.system.preset(pseudo_string = 'abc')
```

INTRO\_CMD\_HELP: Triggers an instrument reset. It has the same effect as:

- The \*RST command
- The 'SGMA-GUI > Instrument Name > Preset' function. However, the command\_ does not close open GUI dialogs like the function does.

```
:param pseudo_string: No help available
```

**preset\_all(pseudo\_string: str)** → None

```
# SCPI: SYSTem:PRESet:ALL
driver.system.preset_all(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
No help available
```

**preset\_base(pseudo\_string: str)** → None

```
# SCPI: SYSTem:PRESet:BASE
driver.system.preset_base(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
No help available
```

**reset(pseudo\_string: str)** → None

```
# SCPI: SYSTem:RESet
driver.system.reset(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**

No help available

**reset\_all**(*pseudo\_string: str*) → None

```
# SCPI: SYSTem:RESet:ALL
driver.system.reset_all(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**

No help available

**reset\_base**(*pseudo\_string: str*) → None

```
# SCPI: SYSTem:RESet:BASE
driver.system.reset_base(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**

No help available

**set\_srestore**(*data\_set: int*) → None

```
# SCPI: SYSTem:SREStore
driver.system.set_srestore(data_set = 1)
```

No command help available

**param data\_set**

No help available

**set\_ssav**(*data\_set: int*) → None

```
# SCPI: SYSTem:SSAVe
driver.system.set_ssav(data_set = 1)
```

No command help available

**param data\_set**

No help available

**set\_tzone**(*pseudo\_string: str*) → None

```
# SCPI: SYSTem:TZONe
driver.system.set_tzone(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**

No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.clone()
```

## Subgroups

### 6.9.1 Date

#### SCPI Commands :

```
SYSTem:DATE:LOCaL
SYSTem:DATE:UTC
```

#### class DateCls

Date commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_local()** → str

```
# SCPI: SYSTem:DATE:LOCaL
value: str = driver.system.date.get_local()
```

No command help available

```
return
pseudo_string: No help available
```

**get\_utc()** → str

```
# SCPI: SYSTem:DATE:UTC
value: str = driver.system.date.get_utc()
```

No command help available

```
return
pseudo_string: No help available
```

**set\_local(pseudo\_string: str)** → None

```
# SCPI: SYSTem:DATE:LOCaL
driver.system.date.set_local(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
No help available
```

**set\_utc(pseudo\_string: str)** → None

```
# SCPI: SYSTem:DATE:UTC
driver.system.date.set_utc(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
No help available
```

## 6.9.2 Device

### SCPI Command :

SYSTem:DEVIce:ID

#### class DeviceCls

Device commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_id()** → str

```
# SCPI: SYSTem:DEVIce:ID
value: str = driver.system.device.get_id()
```

No command help available

**return**  
pseudo\_string: No help available

## 6.9.3 DeviceFootprint

### SCPI Command :

SYSTem:DFPRint

#### class DeviceFootprintCls

DeviceFootprint commands group definition. 3 total commands, 1 Subgroups, 1 group commands

**get()** → str

```
# SCPI: SYSTem:DFPRint
value: str = driver.system.deviceFootprint.get()
```

No command help available

**return**  
device\_footprint: No help available

**set(directory: str)** → None

```
# SCPI: SYSTem:DFPRint
driver.system.deviceFootprint.set(directory = 'abc')
```

No command help available

**param directory**  
No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.deviceFootprint.clone()
```

## Subgroups

### 6.9.3.1 History

#### SCPI Commands :

```
SYSTem:DFPPrint:HISTory:COUNT
SYSTem:DFPPrint:HISTory:ENTRy
```

#### class HistoryCls

History commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_count()** → str

```
# SCPI: SYSTem:DFPPrint:HISTory:COUNT
value: str = driver.system.deviceFootprint.history.get_count()
```

No command help available

```
return
pseudo_string: No help available
```

**get\_entry()** → str

```
# SCPI: SYSTem:DFPPrint:HISTory:ENTRy
value: str = driver.system.deviceFootprint.history.get_entry()
```

No command help available

```
return
pseudo_string: No help available
```

## 6.9.4 Error

#### SCPI Commands :

```
SYSTem:ERRor:ALL
SYSTem:ERRor:COUNT
```

#### class ErrorCls

Error commands group definition. 4 total commands, 1 Subgroups, 2 group commands

**get\_all()** → str

```
# SCPI: SYSTem:ERRor:ALL
value: str = driver.system.error.get_all()
```

Queries the error/event queue for all unread items and removes them from the queue.

**return**

all\_py: string Error/event\_number,'Error/event\_description[;Device-dependent info]'  
A comma separated list of error number and a short description of the error in FIFO order. If the queue is empty, the response is 0,'No error' Positive error numbers are instrument-dependent. Negative error numbers are reserved by the SCPI standard. Volatile errors are reported once, at the time they appear. Identical errors are reported repeatedly only if the original error has already been retrieved from (and hence not any more present in) the error queue.

**get\_count()** → str

```
# SCPI: SYSTem:ERRor:COUNT  
value: str = driver.system.error.get_count()
```

Queries the number of entries in the error queue.

**return**

count: integer 0 The error queue is empty.

## Cloning the Group

```
# Create a clone of the original group, that exists independently  
group2 = driver.system.error.clone()
```

## Subgroups

### 6.9.4.1 Code

#### SCPI Commands :

```
SYSTem:ERRor:CODE:ALL  
SYSTem:ERRor:CODE:[NEXT]
```

**class CodeCls**

Code commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_all()** → str

```
# SCPI: SYSTem:ERRor:CODE:ALL  
value: str = driver.system.error.code.get_all()
```

Queries the error numbers of all entries in the error queue and then deletes them.

**return**

all\_py: string Returns the error numbers. To retrieve the entire error text, send the command method RsSgt.System.Error.all. 0 'No error', i.e. the error queue is empty Positive value Positive error numbers denote device-specific errors Negative value Negative error numbers denote error messages defined by SCPI.

**get\_next()** → str

```
# SCPI: SYSTem:ERRor:CODE:[NEXT]  
value: str = driver.system.error.code.get_next()
```

Queries the error number of the oldest entry in the error queue and then deletes it.

**return**

next\_py: string Returns the error number. To retrieve the entire error text, send the command method RsSgt.System.Error.all. 0 'No error', i.e. the error queue is empty  
Positive value Positive error numbers denote device-specific errors Negative value  
Negative error numbers denote error messages defined by SCPI.

## 6.9.5 Fpreset

### SCPI Command :

```
SYSTem:FPReset
```

#### class FpresetCls

Fpreset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**set()** → None

```
# SCPI: SYSTem:FPReset
driver.system.fpreset.set()
```

Triggers an instrument reset to the original state of delivery.

**set\_with\_opc(opc\_timeout\_ms: int = -1)** → None

```
# SCPI: SYSTem:FPReset
driver.system.fpreset.set_with_opc()
```

Triggers an instrument reset to the original state of delivery.

Same as set, but waits for the operation to complete before continuing further. Use the RsSgt.utilities.opc\_timeout\_set() to set the timeout value.

**param opc\_timeout\_ms**

Maximum time to wait in milliseconds, valid only for this call.

## 6.9.6 Help

### SCPI Command :

```
SYSTem:HELP:HEADers
```

#### class HelpCls

Help commands group definition. 3 total commands, 1 Subgroups, 1 group commands

**get\_headers()** → str

```
# SCPI: SYSTem:HELP:HEADers
value: str = driver.system.help.get_headers()
```

No command help available

**return**

headers: No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.help.clone()
```

## Subgroups

### 6.9.6.1 Syntax

#### SCPI Commands :

```
SYSTem:HELP:SYNTAX:ALL
SYSTem:HELP:SYNTAX
```

#### class SyntaxCls

Syntax commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_all()** → str

```
# SCPI: SYSTem:HELP:SYNTAX:ALL
value: str = driver.system.help.syntax.get_all()
```

No command help available

```
return
    pseudo_string: No help available
```

**get\_value()** → str

```
# SCPI: SYSTem:HELP:SYNTAX
value: str = driver.system.help.syntax.get_value()
```

No command help available

```
return
    pseudo_string: No help available
```

## 6.9.7 Lock

#### SCPI Command :

```
SYSTem:LOCK:TIMEout
```

#### class LockCls

Lock commands group definition. 10 total commands, 5 Subgroups, 1 group commands

**get\_timeout()** → int

```
# SCPI: SYSTem:LOCK:TIMEout
value: int = driver.system.lock.get_timeout()
```

No command help available



**return**  
time\_ms: No help available

**set\_timeout**(time\_ms: int) → None

```
# SCPI: SYSTem:LOCK:TIMEout
driver.system.lock.set_timeout(time_ms = 1)
```

No command help available

**param time\_ms**  
No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.lock.clone()
```

## Subgroups

### 6.9.7.1 Name

#### SCPI Commands :

```
SYSTem:LOCK:NAME:DETAiled
SYSTem:LOCK:NAME
```

#### class NameCls

Name commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_detailed**() → str

```
# SCPI: SYSTem:LOCK:NAME:DETAiled
value: str = driver.system.lock.name.get_detailed()
```

No command help available

**return**  
details: No help available

**get\_value**() → str

```
# SCPI: SYSTem:LOCK:NAME
value: str = driver.system.lock.name.get_value()
```

No command help available

**return**  
name: No help available

### 6.9.7.2 Owner

#### SCPI Commands :

```
SYSTem:LOCK:OWNer:DETAiled
SYSTem:LOCK:OWNer
```

#### class OwnerCls

Owner commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_detailed()** → str

```
# SCPI: SYSTem:LOCK:OWNer:DETAiled
value: str = driver.system.lock.owner.get_detailed()
```

No command help available

**return**  
details: No help available

**get\_value()** → str

```
# SCPI: SYSTem:LOCK:OWNer
value: str = driver.system.lock.owner.get_value()
```

No command help available

**return**  
owner: No help available

### 6.9.7.3 Release

#### SCPI Commands :

```
SYSTem:LOCK:RELease:ALL
SYSTem:LOCK:RELease
```

#### class ReleaseCls

Release commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**set\_all(pseudo\_string: str)** → None

```
# SCPI: SYSTem:LOCK:RELease:ALL
driver.system.lock.release.set_all(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**  
No help available

**set\_value(pseudo\_string: str)** → None

```
# SCPI: SYSTem:LOCK:RELease
driver.system.lock.release.set_value(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**

No help available

#### 6.9.7.4 Request

##### SCPI Command :

```
SYSTem:LOCK:REQuest:[EXCLusive]
```

##### class RequestCls

Request commands group definition. 2 total commands, 1 Subgroups, 1 group commands

**get\_exclusive()** → int

```
# SCPI: SYSTem:LOCK:REQuest:[EXCLusive]
value: int = driver.system.lock.request.get_exclusive()
```

No command help available

**return**

success: No help available

##### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.lock.request.clone()
```

#### Subgroups

##### 6.9.7.4.1 Shared

##### SCPI Command :

```
SYSTem:LOCK:REQuest:SHARed
```

##### class SharedCls

Shared commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get(name: str, timeout\_ms: int)** → int

```
# SCPI: SYSTem:LOCK:REQuest:SHARed
value: int = driver.system.lock.request.shared.get(name = 'abc', timeout_ms = 1)
```

No command help available

**param name**

No help available

**param timeout\_ms**

No help available

**return**  
success: No help available

### 6.9.7.5 Shared

#### SCPI Command :

SYSTem:LOCK:SHARed:STRing

#### class SharedCls

Shared commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_string()** → str

```
# SCPI: SYSTem:LOCK:SHARed:STRing
value: str = driver.system.lock.shared.get_string()
```

No command help available

**return**  
string: No help available

### 6.9.8 Time

#### SCPI Commands :

SYSTem:TIME:LOCal  
SYSTem:TIME:UTC

#### class TimeCls

Time commands group definition. 8 total commands, 2 Subgroups, 2 group commands

**get\_local()** → str

```
# SCPI: SYSTem:TIME:LOCal
value: str = driver.system.time.get_local()
```

No command help available

**return**  
pseudo\_string: No help available

**get\_utc()** → str

```
# SCPI: SYSTem:TIME:UTC
value: str = driver.system.time.get_utc()
```

No command help available

**return**  
pseudo\_string: No help available

**set\_local**(*pseudo\_string*: str) → None

```
# SCPI: SYSTem:TIME:LOCa1
driver.system.time.set_local(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**  
No help available

**set\_utc**(*pseudo\_string*: str) → None

```
# SCPI: SYSTem:TIME:UTC
driver.system.time.set_utc(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**  
No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.clone()
```

## Subgroups

### 6.9.8.1 DaylightSavingTime

#### SCPI Command :

```
SYSTem:TIME:DSTime:MODE
```

#### class DaylightSavingTimeCls

DaylightSavingTime commands group definition. 3 total commands, 1 Subgroups, 1 group commands

**get\_mode**() → str

```
# SCPI: SYSTem:TIME:DSTime:MODE
value: str = driver.system.time.daylightSavingTime.get_mode()
```

No command help available

**return**  
pseudo\_string: No help available

**set\_mode**(*pseudo\_string*: str) → None

```
# SCPI: SYSTem:TIME:DSTime:MODE
driver.system.time.daylightSavingTime.set_mode(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**  
No help available

## Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.daylightSavingTime.clone()
```

## Subgroups

### 6.9.8.1.1 Rule

#### SCPI Commands :

```
SYSTem:TIME:DSTime:RULE:CATalog
SYSTem:TIME:DSTime:RULE
```

#### class RuleCls

Rule commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_catalog()** → str

```
# SCPI: SYSTem:TIME:DSTime:RULE:CATalog
value: str = driver.system.time.daylightSavingTime.rule.get_catalog()
```

No command help available

```
return
pseudo_string: No help available
```

**get\_value()** → str

```
# SCPI: SYSTem:TIME:DSTime:RULE
value: str = driver.system.time.daylightSavingTime.rule.get_value()
```

No command help available

```
return
pseudo_string: No help available
```

**set\_value(pseudo\_string: str)** → None

```
# SCPI: SYSTem:TIME:DSTime:RULE
driver.system.time.daylightSavingTime.rule.set_value(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
No help available
```

### 6.9.8.2 HrTimer

#### SCPI Command :

```
SYSTem:TIME:HRTimer:RELative
```

#### class HrTimerCls

HrTimer commands group definition. 3 total commands, 1 Subgroups, 1 group commands

**set\_relative**(pseudo\_string: str) → None

```
# SCPI: SYSTem:TIME:HRTimer:RELative
driver.system.time.hrTimer.set_relative(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**

No help available

#### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.hrTimer.clone()
```

#### Subgroups

### 6.9.8.2.1 Absolute

#### SCPI Commands :

```
SYSTem:TIME:HRTimer:ABSolute:SET
SYSTem:TIME:HRTimer:ABSolute
```

#### class AbsoluteCls

Absolute commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_set**() → str

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute:SET
value: str = driver.system.time.hrTimer.absolute.get_set()
```

No command help available

**return**

pseudo\_string: No help available

**set\_set**(pseudo\_string: str) → None

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute:SET
driver.system.time.hrTimer.absolute.set_set(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**

No help available

**set\_value**(pseudo\_string: str) → None

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute
driver.system.time.hrTimer.absolute.set_value(pseudo_string = 'abc')
```

No command help available

**param pseudo\_string**

No help available

## 6.10 Test

**class TestCls**

Test commands group definition. 3 total commands, 2 Subgroups, 0 group commands

### Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.clone()
```

### Subgroups

#### 6.10.1 All

**SCPI Commands :**

```
TEST:ALL:RESult
TEST:ALL:STARt
```

**class AllCls**

All commands group definition. 2 total commands, 0 Subgroups, 2 group commands

**get\_result**() → Test

```
# SCPI: TEST:ALL:RESult
value: enums.Test = driver.test.all.get_result()
```

Queries the result of the performed selftest. Start the selftest with method RsSgt.Test.All.start.

**return**

result: 0| 1| RUNning| STOPped

**start**() → None

```
# SCPI: TEST:ALL:STARt
driver.test.all.start()
```

Starts the selftest. Use the command method RsSgt.Test.All.result to query the result.



**start\_with\_opc**(*opc\_timeout\_ms: int = -1*) → None

```
# SCPI: TEST:ALL:START
driver.test.all.start_with_opc()
```

Starts the selftest. Use the command method RsSgt.Test.All.result to query the result.

Same as start, but waits for the operation to complete before continuing further. Use the RsSgt.utilities.opc\_timeout\_set() to set the timeout value.

**param opc\_timeout\_ms**

Maximum time to wait in milliseconds, valid only for this call.

## 6.10.2 Keyboard

**SCPI Command :**

```
TEST:KEYBoard:[STATE]
```

**class KeyboardCls**

Keyboard commands group definition. 1 total commands, 0 Subgroups, 1 group commands

**get\_state**() → bool

```
# SCPI: TEST:KEYBoard:[STATE]
value: bool = driver.test.keyboard.get_state()
```

Enable/disable keyboard and LED test state.

**return**

state: 1| ON| 0| OFF

**set\_state**(*state: bool*) → None

```
# SCPI: TEST:KEYBoard:[STATE]
driver.test.keyboard.set_state(state = False)
```

Enable/disable keyboard and LED test state.

**param state**

1| ON| 0| OFF



## RSSGT UTILITIES

### class Utilities

Common utility class. Utility functions common for all types of drivers.

Access snippet: `utils = RsSgt.utilities`

**property logger:** *ScpiLogger*

Scpi Logger interface, see [here](#)

Access snippet: `logger = RsSgt.utilities.logger`

**property driver\_version:** `str`

Returns the instrument driver version.

**property idn\_string:** `str`

Returns instrument's identification string - the response on the SCPI command `*IDN?`

**property manufacturer:** `str`

Returns manufacturer of the instrument.

**property full\_instrument\_model\_name:** `str`

Returns the current instrument's full name e.g. 'FSW26'.

**property instrument\_model\_name:** `str`

Returns the current instrument's family name e.g. 'FSW'.

**property supported\_models:** `List[str]`

Returns a list of the instrument models supported by this instrument driver.

**property instrument\_firmware\_version:** `str`

Returns instrument's firmware version.

**property instrument\_serial\_number:** `str`

Returns instrument's serial\_number.

**query\_opc**(*timeout: int = 0*) → `int`

SCPI command: `*OPC?` Queries the instrument's OPC bit and hence it waits until the instrument reports operation complete. If you define `timeout > 0`, the VISA timeout is set to that value just for this method call.

**property instrument\_status\_checking:** `bool`

Sets / returns Instrument Status Checking. When True (default is True), all the driver methods and properties are sending "SYSTem:ERRor?" at the end to immediately react on error that might have occurred. We recommend to keep the state checking ON all the time. Switch it OFF only in rare cases when you require maximum speed. The default state after initializing the session is ON.

**property encoding: str**

Returns string<=>bytes encoding of the session.

**property opc\_query\_after\_write: bool**

Sets / returns Instrument *\*OPC?* query sending after each command write. When True, (default is False) the driver sends *\*OPC?* every time a write command is performed. Use this if you want to make sure your sequence is performed command-after-command.

**property bin\_float\_numbers\_format: BinFloatFormat**

Sets / returns format of float numbers when transferred as binary data.

**property bin\_int\_numbers\_format: BinIntFormat**

Sets / returns format of integer numbers when transferred as binary data.

**clear\_status()** → None

Clears instrument's status system, the session's I/O buffers and the instrument's error queue.

**query\_all\_errors()** → List[str]

Queries and clears all the errors from the instrument's error queue. The method returns list of strings as error messages. If no error is detected, the return value is None. The process is: querying 'SYS-Tem:ERRor?' in a loop until the error queue is empty. If you want to include the error codes, call the `query_all_errors_with_codes()`

**query\_all\_errors\_with\_codes()** → List[Tuple[int, str]]

Queries and clears all the errors from the instrument's error queue. The method returns list of tuples (code: int, message: str). If no error is detected, the return value is None. The process is: querying 'SYS-Tem:ERRor?' in a loop until the error queue is empty.

**property instrument\_options: List[str]**

Returns all the instrument options. The options are sorted in the ascending order starting with K-options and continuing with B-options.

**reset()** → None

SCPI command: *\*RST* Sends *\*RST* command + calls the `clear_status()`.

**default\_instrument\_setup()** → None

Custom steps performed at the init and at the reset().

**self\_test(timeout: int = None)** → Tuple[int, str]

SCPI command: *\*TST?* Performs instrument's self-test. Returns tuple (code:int, message: str). Code 0 means the self-test passed. You can define the custom timeout in milliseconds. If you do not define it, the default selftest timeout is used (usually 60 secs).

**is\_connection\_active()** → bool

Returns true, if the VISA connection is active and the communication with the instrument still works.

**reconnect(force\_close: bool = False)** → bool

If the connection is not active, the method tries to reconnect to the device. If the connection is active, and `force_close` is False, the method does nothing. If the connection is active, and `force_close` is True, the method closes, and opens the session again. Returns True, if the reconnection has been performed.

**property resource\_name: int**

Returns the resource name used in the constructor

**property opc\_timeout: int**

Sets / returns timeout in milliseconds for all the operations that use OPC synchronization.

**property visa\_timeout: int**

Sets / returns visa IO timeout in milliseconds.

**property data\_chunk\_size: int**

Sets / returns the maximum size of one block transferred during write/read operations

**property visa\_manufacturer: int**

Returns the manufacturer of the current VISA session.

**process\_all\_commands()** → None

SCPI command: \*WAI Stops further commands processing until all commands sent before \*WAI have been executed.

**write\_str(cmd: str)** → None

Writes the command to the instrument.

**write(cmd: str)** → None

This method is an alias to the write\_str(). Writes the command to the instrument as string.

**write\_int(cmd: str, param: int)** → None

Writes the command to the instrument followed by the integer parameter: e.g.: cmd = 'SELECT:INPUT' param = '2', result command = 'SELECT:INPUT 2'

**write\_int\_with\_opc(cmd: str, param: int, timeout: int = None)** → None

Writes the command with OPC to the instrument followed by the integer parameter: e.g.: cmd = 'SELECT:INPUT' param = '2', result command = 'SELECT:INPUT 2' If you do not provide timeout, the method uses current opc\_timeout.

**write\_float(cmd: str, param: float)** → None

Writes the command to the instrument followed by the boolean parameter: e.g.: cmd = 'CENTER:FREQ' param = '10E6', result command = 'CENTER:FREQ 10E6'

**write\_float\_with\_opc(cmd: str, param: float, timeout: int = None)** → None

Writes the command with OPC to the instrument followed by the boolean parameter: e.g.: cmd = 'CENTER:FREQ' param = '10E6', result command = 'CENTER:FREQ 10E6' If you do not provide timeout, the method uses current opc\_timeout.

**write\_bool(cmd: str, param: bool)** → None

Writes the command to the instrument followed by the boolean parameter: e.g.: cmd = 'OUTPUT' param = 'True', result command = 'OUTPUT ON'

**write\_bool\_with\_opc(cmd: str, param: bool, timeout: int = None)** → None

Writes the command with OPC to the instrument followed by the boolean parameter: e.g.: cmd = 'OUTPUT' param = 'True', result command = 'OUTPUT ON' If you do not provide timeout, the method uses current opc\_timeout.

**query\_str(query: str)** → str

Sends the query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit.

**query(query: str)** → str

This method is an alias to the query\_str(). Sends the query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit.

**query\_bool(query: str)** → bool

Sends the query to the instrument and returns the response as boolean.

**query\_int**(*query: str*) → int

Sends the query to the instrument and returns the response as integer.

**query\_float**(*query: str*) → float

Sends the query to the instrument and returns the response as float.

**write\_str\_with\_opc**(*cmd: str, timeout: int = None*) → None

Writes the opc-synced command to the instrument. If you do not provide timeout, the method uses current `opc_timeout`.

**write\_with\_opc**(*cmd: str, timeout: int = None*) → None

This method is an alias to the `write_str_with_opc()`. Writes the opc-synced command to the instrument. If you do not provide timeout, the method uses current `opc_timeout`.

**query\_str\_with\_opc**(*query: str, timeout: int = None*) → str

Sends the opc-synced query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit. If you do not provide timeout, the method uses current `opc_timeout`.

**query\_with\_opc**(*query: str, timeout: int = None*) → str

This method is an alias to the `query_str_with_opc()`. Sends the opc-synced query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit. If you do not provide timeout, the method uses current `opc_timeout`.

**query\_bool\_with\_opc**(*query: str, timeout: int = None*) → bool

Sends the opc-synced query to the instrument and returns the response as boolean. If you do not provide timeout, the method uses current `opc_timeout`.

**query\_int\_with\_opc**(*query: str, timeout: int = None*) → int

Sends the opc-synced query to the instrument and returns the response as integer. If you do not provide timeout, the method uses current `opc_timeout`.

**query\_float\_with\_opc**(*query: str, timeout: int = None*) → float

Sends the opc-synced query to the instrument and returns the response as float. If you do not provide timeout, the method uses current `opc_timeout`.

**write\_bin\_block**(*cmd: str, payload: bytes*) → None

Writes all the payload as binary data block to the instrument. The binary data header is added at the beginning of the transmission automatically, do not include it in the payload!!!

**query\_bin\_block**(*query: str*) → bytes

Queries binary data block to bytes. Throws an exception if the returned data was not a binary data. Returns `data:bytes`

**query\_bin\_block\_with\_opc**(*query: str, timeout: int = None*) → bytes

Sends a OPC-synced query and returns binary data block to bytes. If you do not provide timeout, the method uses current `opc_timeout`.

**query\_bin\_or\_ascii\_float\_list**(*query: str*) → List[float]

Queries a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property `BinFloatFormat`, usually float 32-bit (FORM REAL,32).

**query\_bin\_or\_ascii\_float\_list\_with\_opc**(*query: str, timeout: int = None*) → List[float]

Sends a OPC-synced query and reads a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property `BinFloatFormat`, usually float 32-bit (FORM REAL,32). If you do not provide timeout, the method uses current `opc_timeout`.

**query\_bin\_or\_ascii\_int\_list**(*query: str*) → List[int]

Queries a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property BinFloatFormat, usually float 32-bit (FORM REAL,32).

**query\_bin\_or\_ascii\_int\_list\_with\_opc**(*query: str, timeout: int = None*) → List[int]

Sends a OPC-synced query and reads a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property BinFloatFormat, usually float 32-bit (FORM REAL,32). If you do not provide timeout, the method uses current `opc_timeout`.

**query\_bin\_block\_to\_file**(*query: str, file\_path: str, append: bool = False*) → None

Queries binary data block to the provided file. If `append` is `False`, any existing file content is discarded. If `append` is `True`, the new content is added to the end of the existing file, or if the file does not exist, it is created. Throws an exception if the returned data was not a binary data. Example for transferring a file from Instrument -> PC: `query = f"MMEM:DATA? '{INSTR_FILE_PATH}'"`. Alternatively, use the dedicated methods for this purpose:

- `send_file_from_pc_to_instrument()`
- `read_file_from_instrument_to_pc()`

**query\_bin\_block\_to\_file\_with\_opc**(*query: str, file\_path: str, append: bool = False, timeout: int = None*) → None

Sends a OPC-synced query and writes the returned data to the provided file. If `append` is `False`, any existing file content is discarded. If `append` is `True`, the new content is added to the end of the existing file, or if the file does not exist, it is created. Throws an exception if the returned data was not a binary data.

**write\_bin\_block\_from\_file**(*cmd: str, file\_path: str*) → None

Writes data from the file as binary data block to the instrument using the provided command. Example for transferring a file from PC -> Instrument: `cmd = f"MMEM:DATA '{INSTR_FILE_PATH}'"`. Alternatively, use the dedicated methods for this purpose:

- `send_file_from_pc_to_instrument()`
- `read_file_from_instrument_to_pc()`

**send\_file\_from\_pc\_to\_instrument**(*source\_pc\_file: str, target\_instr\_file: str*) → None

SCPI Command: `MMEM:DATA`

Sends file from PC to the instrument

**read\_file\_from\_instrument\_to\_pc**(*source\_instr\_file: str, target\_pc\_file: str, append\_to\_pc\_file: bool = False*) → None

SCPI Command: `MMEM:DATA?`

Reads file from instrument to the PC.

Set the `append_to_pc_file` to `True` if you want to append the read content to the end of the existing PC file

**get\_last\_sent\_cmd**() → str

Returns the last commands sent to the instrument. Only works in simulation mode

**go\_to\_local**() → None

Puts the instrument into local state.

**go\_to\_remote**() → None

Puts the instrument into remote state.

**get\_lock()** → RLock

Returns the thread lock for the current session.

**By default:**

- If you create standard new RsSgt instance with new VISA session, the session gets a new thread lock. You can assign it to other RsSgt sessions in order to share one physical instrument with a multi-thread access.
- If you create new RsSgt from an existing session, the thread lock is shared automatically making both instances multi-thread safe.

You can always assign new thread lock by calling `driver.utilities.assign_lock()`

**assign\_lock(lock: RLock)** → None

Assigns the provided thread lock.

**clear\_lock()**

Clears the existing thread lock, making the current session thread-independent from others that might share the current thread lock.

**sync\_from(source: Utilities)** → None

Synchronises these Utils with the source.



## RSSGT LOGGER

Check the usage in the Getting Started chapter [here](#).

### **class ScpiLogger**

Base class for SCPI logging

#### **mode**

Sets the logging ON or OFF. Additionally, you can set the logging ON only for errors. Possible values:

- `LoggingMode.Off` - logging is switched OFF
- `LoggingMode.On` - logging is switched ON
- `LoggingMode.Errors` - logging is switched ON, but only for error entries
- `LoggingMode.Default` - sets the logging to default - the value you have set with `logger.default_mode`

#### **default\_mode**

Sets / returns the default logging mode. You can recall the default mode by calling the `logger.mode = LoggingMode.Default`.

#### **Data Type**

`LoggingMode`

#### **device\_name: str**

Use this property to change the resource name in the log from the default Resource Name (e.g. `TCPIP::192.168.2.101::INSTR`) to another name e.g. `'MySigGen1'`.

#### **set\_logging\_target(target, console\_log: bool = None, udp\_log: bool = None) → None**

Sets logging target - the target must implement `write()` and `flush()`. You can optionally set the console and UDP logging ON or OFF. This method switches the logging target global OFF.

#### **get\_logging\_target()**

Based on the `global_mode`, it returns the logging target: either the local or the global one.

#### **set\_logging\_target\_global(console\_log: bool = None, udp\_log: bool = None) → None**

Sets logging target to global. The global target must be defined. You can optionally set the console and UDP logging ON or OFF.

#### **log\_to\_console**

Returns logging to console status.

#### **log\_to\_udp**

Returns logging to UDP status.

#### **log\_to\_console\_and\_udp**

Returns true, if both logging to UDP and console in are True.

**info\_raw**(log\_entry: str, add\_new\_line: bool = True) → None

Method for logging the raw string without any formatting.

**info**(start\_time: datetime, end\_time: datetime, log\_string\_info: str, log\_string: str) → None

Method for logging one info entry. For binary log\_string, use the info\_bin()

**error**(start\_time: datetime, end\_time: datetime, log\_string\_info: str, log\_string: str) → None

Method for logging one error entry.

**set\_relative\_timestamp**(timestamp: datetime) → None

If set, the further timestamps will be relative to the entered time.

**set\_relative\_timestamp\_now**() → None

Sets the relative timestamp to the current time.

**get\_relative\_timestamp**() → datetime

Based on the global\_mode, it returns the relative timestamp: either the local or the global one.

**clear\_relative\_timestamp**() → None

Clears the reference time, and the further logging continues with absolute times.

**flush**() → None

Flush all the entries.

**log\_status\_check\_ok**

Sets / returns the current status of status checking OK. If True (default), the log contains logging of the status checking 'Status check: OK'. If False, the 'Status check: OK' is skipped - the log is more compact. Errors will still be logged.

**clear\_cached\_entries**() → None

Clears potential cached log entries. Cached log entries are generated when the Logging is ON, but no target has been defined yet.

**set\_format\_string**(value: str, line\_divider: str = '\n') → None

Sets new format string and line divider. If you just want to set the line divider, set the format string value=None. The original format string is: PAD\_LEFT12(%START\_TIME%) PAD\_LEFT25(%DEVICE\_NAME%) PAD\_LEFT12(%DURATION%) %LOG\_STRING\_INFO% %LOG\_STRING%

**restore\_format\_string**() → None

Restores the original format string and the line divider to LF

**abbreviated\_max\_len\_ascii: int**

Defines the maximum length of one ASCII log entry. Default value is 200 characters.

**abbreviated\_max\_len\_bin: int**

Defines the maximum length of one Binary log entry. Default value is 2048 bytes.

**abbreviated\_max\_len\_list: int**

Defines the maximum length of one list entry. Default value is 100 elements.

**bin\_line\_block\_size: int**

Defines number of bytes to display in one line. Default value is 16 bytes.

**udp\_port**

Returns udp logging port.

**target\_auto\_flushing**

Returns status of the auto-flushing for the logging target.

## RSSGT EVENTS

Check the usage in the Getting Started chapter [here](#).

### **class Events**

Common Events class. Event-related methods and properties. Here you can set all the event handlers.

**property before\_query\_handler: Callable**

Returns the handler of before\_query events.

**Returns**

current before\_query\_handler

**property before\_write\_handler: Callable**

Returns the handler of before\_write events.

**Returns**

current before\_write\_handler

**property io\_events\_include\_data: bool**

Returns the current state of the io\_events\_include\_data See the setter for more details.

**property on\_read\_handler: Callable**

Returns the handler of on\_read events.

**Returns**

current on\_read\_handler

**property on\_write\_handler: Callable**

Returns the handler of on\_write events.

**Returns**

current on\_write\_handler

**sync\_from**(source: Events) → None

Synchronises these Events with the source.



---

**CHAPTER  
TEN**

---

**INDEX**



# INDEX

## Symbols

[SOURCE<HW>]:BB:FOFFset, 64  
 [SOURCE<HW>]:BB:POFFset, 64  
 [SOURCE<HW>]:BBIN:ODELay, 73  
 [SOURCE<HW>]:BBIN:SRATe:[ACTual], 74  
 [SOURCE<HW>]:FREQuency:[CW], 75  
 [SOURCE<HW>]:FREQuency:[CW]:RCL, 75  
 [SOURCE<HW>]:FREQuency:[CW]:STEP:MODE, 76  
 [SOURCE<HW>]:FREQuency:[CW]:STEP:[INCRement], 76  
 [SOURCE<HW>]:FREQuency:[FIXed], 77  
 [SOURCE<HW>]:FREQuency:[FIXed]:RCL, 77  
 [SOURCE<HW>]:FREQuency:[FIXed]:STEP:MODE, 78  
 [SOURCE<HW>]:FREQuency:[FIXed]:STEP:[INCRement], 78  
 [SOURCE<HW>]:INPut:TRIGger:IMPedance, 80  
 [SOURCE<HW>]:INPut:TRIGger:LEVel, 80  
 [SOURCE<HW>]:INPut:TRIGger:[BBAND]:SLOPe, 81  
 [SOURCE<HW>]:IQ:CREStfactor, 81  
 [SOURCE<HW>]:IQ:IMPairment:IQRatio:[MAGNitude], 84  
 [SOURCE<HW>]:IQ:IMPairment:LEAKage:I, 84  
 [SOURCE<HW>]:IQ:IMPairment:LEAKage:Q, 84  
 [SOURCE<HW>]:IQ:IMPairment:QUADrature:[ANGLE], 85  
 [SOURCE<HW>]:IQ:IMPairment:SWAP:[STATe], 86  
 [SOURCE<HW>]:IQ:IMPairment:[STATe], 83  
 [SOURCE<HW>]:IQ:SOURce, 81  
 [SOURCE<HW>]:IQ:STATe, 81  
 [SOURCE<HW>]:IQ:WBSTate, 81  
 [SOURCE<HW>]:LOSCillator:SOURce, 86  
 [SOURCE<HW>]:OPMode, 64  
 [SOURCE<HW>]:PHASe, 87  
 [SOURCE<HW>]:PHASe:REFeRence, 88  
 [SOURCE<HW>]:POWER:ALC:DSensitivity, 90  
 [SOURCE<HW>]:POWER:ALC:SONCe, 91  
 [SOURCE<HW>]:POWER:ALC:[STATe], 90  
 [SOURCE<HW>]:POWER:ATTenuation:DIGital, 92  
 [SOURCE<HW>]:POWER:ATTenuation:RFOFF:MODE, 92  
 [SOURCE<HW>]:POWER:ATTenuation:SOVer:[OFFSet], 93  
 [SOURCE<HW>]:POWER:LIMit:[AMPLitude], 95  
 [SOURCE<HW>]:POWER:LMODe, 88  
 [SOURCE<HW>]:POWER:PEP, 88  
 [SOURCE<HW>]:POWER:POWER, 88  
 [SOURCE<HW>]:POWER:RANGe:LOWer, 96  
 [SOURCE<HW>]:POWER:RANGe:UPPer, 96  
 [SOURCE<HW>]:POWER:SCHARacteristic, 88  
 [SOURCE<HW>]:POWER:SERVoing:SENSor, 99  
 [SOURCE<HW>]:POWER:SERVoing:SENSor:APERture, 99  
 [SOURCE<HW>]:POWER:SERVoing:SET, 96  
 [SOURCE<HW>]:POWER:SERVoing:STATe, 96  
 [SOURCE<HW>]:POWER:SERVoing:TARGet, 96  
 [SOURCE<HW>]:POWER:SERVoing:TEST, 96  
 [SOURCE<HW>]:POWER:SERVoing:TOLerance, 96  
 [SOURCE<HW>]:POWER:SERVoing:TRACking, 96  
 [SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:OFFSet, 94  
 [SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:RCL, 94  
 [SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:[AMPLitude], 94  
 [SOURCE<HW>]:ROSCillator:EXTernal:FREQuency, 100  
 [SOURCE<HW>]:ROSCillator:OUTPut:FREQuency, 101  
 [SOURCE<HW>]:ROSCillator:SOURce, 100  
 [SOURCE]:BB:IMPairment:BBMM<CH>:POFFset, 66  
 [SOURCE]:BB:IMPairment:IQOutput<CH>:IQRatio:[MAGNitude], 68  
 [SOURCE]:BB:IMPairment:IQOutput<CH>:LEAKage:I, 69  
 [SOURCE]:BB:IMPairment:IQOutput<CH>:LEAKage:Q, 70  
 [SOURCE]:BB:IMPairment:IQOutput<CH>:QUADrature:[ANGLE], 71  
 [SOURCE]:BB:IMPairment:IQOutput<CH>:STATe, 72  
 [SOURCE]:FREQuency:OFFSet, 74  
 [SOURCE]:INPut:MODext:IMPedance, 79

## A

abbreviated\_max\_len\_ascii (*ScpiLogger attribute*), 140

abbreviated\_max\_len\_bin (*ScpiLogger attribute*),  
140  
abbreviated\_max\_len\_list (*ScpiLogger attribute*),  
140

## B

bin\_line\_block\_size (*ScpiLogger attribute*), 140

## C

CALibration:ALL:[MEASure], 43  
CALibration:FREQuency:TEMPerature, 44  
CALibration:FREQuency:[MEASure], 44  
CALibration:IQModulator:BBAND:[STATe], 45  
CALibration:IQModulator:FULL, 44  
CALibration:IQModulator:IQModulator:[STATe],  
46  
CALibration:IQModulator:LOCAl, 44  
CALibration:IQModulator:TEMPerature, 44  
CALibration:LEVel:TEMPerature, 46  
CALibration:LEVel:[MEASure], 46  
clear\_cached\_entries() (*ScpiLogger method*), 140  
clear\_relative\_timestamp() (*ScpiLogger method*),  
140  
CONNector:REFLo:OUTPut, 47  
CONNector:USER<CH>:CLOCK:IMPedance, 48  
CONNector:USER<CH>:CLOCK:SLOPe, 49  
CONNector:USER<CH>:OMODE, 50  
CONNector:USER<CH>:THReshold, 51  
CONNector:USER<CH>:TRIGger:IMPedance, 51  
CONNector:USER<CH>:TRIGger:SLOPe, 52

## D

default\_mode (*ScpiLogger attribute*), 139  
device\_name (*ScpiLogger attribute*), 139  
DIAGnostic:POINt:CATalog, 53

## E

error() (*ScpiLogger method*), 140

## F

flush() (*ScpiLogger method*), 140

## G

get\_logging\_target() (*ScpiLogger method*), 139  
get\_relative\_timestamp() (*ScpiLogger method*),  
140

## I

info() (*ScpiLogger method*), 140  
info\_raw() (*ScpiLogger method*), 139

## L

log\_status\_check\_ok (*ScpiLogger attribute*), 140

log\_to\_console (*ScpiLogger attribute*), 139  
log\_to\_console\_and\_udp (*ScpiLogger attribute*), 139  
log\_to\_udp (*ScpiLogger attribute*), 139

## M

MMEMory:CATalog, 56  
MMEMory:CATalog:LENGth, 57  
MMEMory:CDIRectory, 54  
MMEMory:COPY, 54  
MMEMory:DCATalog, 57  
MMEMory:DCATalog:LENGth, 58  
MMEMory:DELeTe, 54  
MMEMory:DRIVes, 54  
MMEMory:LOAD:STATe, 59  
MMEMory:MDIRectory, 54  
MMEMory:MOVE, 54  
MMEMory:MSIS, 54  
MMEMory:RDIRectory, 54  
MMEMory:RDIRectory:RECURSive, 54  
MMEMory:STORe:STATe, 59  
mode (*ScpiLogger attribute*), 139

## O

OUTPut<HW>:AFIXed:RANGe:LOWer, 61  
OUTPut<HW>:AFIXed:RANGe:UPPer, 61  
OUTPut<HW>:AMODE, 60  
OUTPut<HW>:PROTection:CLEAr, 62  
OUTPut<HW>:[STATe], 62  
OUTPut<HW>:[STATe]:PON, 62

## R

restore\_format\_string() (*ScpiLogger method*), 140

## S

SCONfiguration:MODE, 63  
ScpiLogger (*class in RsSgt.Internal.ScpiLogger*), 139  
set\_format\_string() (*ScpiLogger method*), 140  
set\_logging\_target() (*ScpiLogger method*), 139  
set\_logging\_target\_global() (*ScpiLogger method*),  
139  
set\_relative\_timestamp() (*ScpiLogger method*),  
140  
set\_relative\_timestamp\_now() (*ScpiLogger method*), 140  
STATus:OPERation:BIT<BITNR>:CONDition, 105  
STATus:OPERation:BIT<BITNR>:ENABLe, 106  
STATus:OPERation:BIT<BITNR>:NTRAnsition, 107  
STATus:OPERation:BIT<BITNR>:PTRAnsition, 107  
STATus:OPERation:BIT<BITNR>:[EVENT], 106  
STATus:OPERation:CONDition, 102  
STATus:OPERation:ENABLe, 102  
STATus:OPERation:NTRAnsition, 102  
STATus:OPERation:PTRAnsition, 102



STATUS:OPERation:[EVENT], 102  
 STATUS:PRESet, 102  
 STATUS:QUESTionable:BIT<BITNR>:CONDition, 111  
 STATUS:QUESTionable:BIT<BITNR>:ENABLE, 111  
 STATUS:QUESTionable:BIT<BITNR>:NTRansition,  
 112  
 STATUS:QUESTionable:BIT<BITNR>:PTRansition,  
 113  
 STATUS:QUESTionable:BIT<BITNR>:[EVENT], 112  
 STATUS:QUESTionable:CONDition, 108  
 STATUS:QUESTionable:ENABLE, 108  
 STATUS:QUESTionable:NTRansition, 108  
 STATUS:QUESTionable:PTRansition, 108  
 STATUS:QUESTionable:[EVENT], 108  
 STATUS:QUEue:[NEXT], 114  
 SYSTem:DATE:LOCAl, 117  
 SYSTem:DATE:UTC, 117  
 SYSTem:DEvice:ID, 118  
 SYSTem:DFPPrint, 118  
 SYSTem:DFPPrint:HISTory:COUNt, 119  
 SYSTem:DFPPrint:HISTory:ENTRy, 119  
 SYSTem:DID, 114  
 SYSTem:ERRor:ALL, 119  
 SYSTem:ERRor:CODE:ALL, 120  
 SYSTem:ERRor:CODE:[NEXT], 120  
 SYSTem:ERRor:COUNt, 119  
 SYSTem:FPReset, 121  
 SYSTem:HELP:HEADers, 121  
 SYSTem:HELP:SYNTax, 122  
 SYSTem:HELP:SYNTax:ALL, 122  
 SYSTem:LOCK:NAME, 123  
 SYSTem:LOCK:NAME:DETAiled, 123  
 SYSTem:LOCK:OWNer, 124  
 SYSTem:LOCK:OWNer:DETAiled, 124  
 SYSTem:LOCK:RELease, 124  
 SYSTem:LOCK:RELease:ALL, 124  
 SYSTem:LOCK:REQuest:SHARed, 125  
 SYSTem:LOCK:REQuest:[EXCLusive], 125  
 SYSTem:LOCK:SHARed:STRing, 126  
 SYSTem:LOCK:TIMEout, 122  
 SYSTem:PRESet, 114  
 SYSTem:PRESet:ALL, 114  
 SYSTem:PRESet:BASE, 114  
 SYSTem:RESet, 114  
 SYSTem:RESet:ALL, 114  
 SYSTem:RESet:BASE, 114  
 SYSTem:SREStore, 114  
 SYSTem:SSAVe, 114  
 SYSTem:TIME:DSTime:MODE, 127  
 SYSTem:TIME:DSTime:RULE, 128  
 SYSTem:TIME:DSTime:RULE:CATalog, 128  
 SYSTem:TIME:HRTimer:ABSolute, 129  
 SYSTem:TIME:HRTimer:ABSolute:SET, 129  
 SYSTem:TIME:HRTimer:RELative, 129

SYSTem:TIME:LOCAl, 126  
 SYSTem:TIME:UTC, 126  
 SYSTem:TZONE, 114  
 SYSTem:VERSion, 114

## T

target\_auto\_flushing (*ScpiLogger attribute*), 140  
 TEST:ALL:RESult, 130  
 TEST:ALL:START, 130  
 TEST:KEYBoard:[STATe], 131

## U

udp\_port (*ScpiLogger attribute*), 140